Launch Control XL 3 — Ambient Perkussion 1 (lab/drums, 007: Jojo 6 instead of the ticks)

Candidates for Jojo 6 in track 007, over 007's context (Mode 2: heartbeat, drone, pad). Real recordings only. Pick by ear: which 1–2 go on?

Knob Fader Button unused

Mode 16 — Candidates

	1 Kalimba	2 Shaker	3 Slit Drum	4 Birds	5 Pebbles	6 Fire	7 Gong	8 Tubular Bells
Row 1 Brightness	CC 13 **Brightness** soft ↔ bright (low-pass).	CC 14 **Brightness** as 1 Kalimba	CC 15 **Brightness** as 1 Kalimba	CC 16 **Brightness** as 1 Kalimba	CC 17 **Brightness** as 1 Kalimba	CC 18 **Brightness** as 1 Kalimba	CC 19 **Brightness** as 1 Kalimba	CC 20 **Brightness** as 1 Kalimba
Row 2 Space	CC 21 **Space** room and dotted-8th echo (a little at 0).	CC 22 **Space** as 1 Kalimba	CC 23 **Space** as 1 Kalimba	CC 24 **Space** as 1 Kalimba	CC 25 **Space** as 1 Kalimba	CC 26 **Space** as 1 Kalimba	CC 27 **Space** as 1 Kalimba	CC 28 **Space** as 1 Kalimba
Row 3 Character	CC 29 **Density** 0 = the figure ↔ + a soft high voice in between.	CC 30 **Density** 0 = the figure ↔ + quiet 16ths, from the middle a cabasa on 4.	CC 31 **Density** 0 = the figure ↔ + soft ghost strokes on the high tongue.	CC 32 **Density** 0 = a bird now and then ↔ many.	CC 33 **Density** 0 = the figure ↔ + trickling 16ths.	CC 34 **Density** 0 = a few pops ↔ crackling all the time.	CC 35 **Depth** 0 = as recorded ↔ an octave lower, bigger and darker.	CC 36 **Density** 0 = the figure ↔ + soft strokes an octave up.
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Kalimba	CC 7 **Level** as 1 Kalimba	CC 8 **Level** as 1 Kalimba	CC 9 **Level** as 1 Kalimba	CC 10 **Level** as 1 Kalimba	CC 11 **Level** as 1 Kalimba	CC 12 **Level** as 1 Kalimba
Button 1 Change	CC 37 **Change** calm → two hands → circling (5 against 8).	CC 38 **Change** 8ths → 16ths → rocking 3-3-2.	CC 39 **Change** call → answer → walking.	CC 40 **Change** single → call and answer → dawn chorus.	CC 41 **Change** footsteps → trickle → pushed.	CC 42 **Change** embers → crackle → loop.	CC 43 **Change** every 2 bars → call → low + light.	CC 44 **Change** root → call → ringing.
Button 2 Moment	CC 45 **Echo throw** held: long dotted-8th echo.	CC 46 **Echo throw** as 1 Kalimba	CC 47 **Echo throw** as 1 Kalimba	CC 48 **Echo throw** as 1 Kalimba	CC 49 **Echo throw** as 1 Kalimba	CC 50 **Echo throw** as 1 Kalimba	CC 51 **Echo throw** as 1 Kalimba	CC 52 **Echo throw** as 1 Kalimba

Mode 2 — Context

	1	2	3	4	5 Progression	6 Heartbeat	7 Drone	8 Pad
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 —	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Heartbeat** 007's soft pulse on D.	CC 59 **Drone** D–A drone, swelling every 2 bars.	CC 60 **Pad** 007's pad, high-passed (less mud).
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Progression** next of 3, at the next 8 bars.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 **Back** previous progression.	CC 98 **Pulse out** the pulse pauses while held.	CC 99 —	CC 100 —

Generated from `lab/drums/ambient-perkussion-1.strudel` — edit the `@ctl` comments in the track, not this sheet.

Guide

What to listen for

Does it sit under the pad and the heartbeat without ticking like a clock? Organic percussion (1–3), field recordings (4–6) or gongs/bells (7–8)?