Launch Control XL 3 — Techno-Akkorde 1 (lab/harmonie, 008 Jonas 2: chord candidates after research)

Column 1 = the chord pulse as it is in 008 (reference). Columns 2–7 = one researched recipe each (see the file head).

Context in Mode 2: drums, bass and pad of 008, the progression on column 5 button 1.

Knob Fader Button unused

Mode 16 — Candidates

	1 Puls (jetzt)	2 Dub-Chuff	3 Basic Ch.	4 Parallel	5 Pad gehackt	6 Ein Schlag	7 Dreiklang	8
Row 1 Brightness	CC 13 **Brightness** dark ↔ open (low-pass, range per column).	CC 14 **Brightness** as 1 Puls (jetzt)	CC 15 **Brightness** as 1 Puls (jetzt)	CC 16 **Brightness** as 1 Puls (jetzt)	CC 17 **Brightness** as 1 Puls (jetzt)	CC 18 **Brightness** as 1 Puls (jetzt)	CC 19 **Brightness** as 1 Puls (jetzt)	CC 20 —
Row 2 Space	CC 21 **Space** a little room ↔ far away; columns 2, 3, 5, 6 also more of their echo.	CC 22 **Space** as 1 Puls (jetzt)	CC 23 **Space** as 1 Puls (jetzt)	CC 24 **Space** as 1 Puls (jetzt)	CC 25 **Space** as 1 Puls (jetzt)	CC 26 **Space** as 1 Puls (jetzt)	CC 27 **Space** as 1 Puls (jetzt)	CC 28 —
Row 3 Character	CC 29 **Length** short pulses ↔ longer (note length).	CC 30 **Echo tail** short echo ↔ long tape echo tail (feedback 0.35–0.8).	CC 31 **Band** low, hollow ↔ high, thin (bandpass centre 300–2000 Hz, moving slowly).	CC 32 **Length** short stabs ↔ longer.	CC 33 **Drive** clean ↔ driven chord in the 5/16 echo.	CC 34 **Echo tail** a few repeats ↔ a long trail (feedback 0.4–0.85).	CC 35 **Length** short stabs ↔ longer.	CC 36 —
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Puls (jetzt)	CC 7 **Level** as 1 Puls (jetzt)	CC 8 **Level** as 1 Puls (jetzt)	CC 9 **Level** as 1 Puls (jetzt)	CC 10 **Level** as 1 Puls (jetzt)	CC 11 **Level** as 1 Puls (jetzt)	CC 12 —
Button 1 Rhythm	CC 37 **Rhythm** three rhythms per column, at the next bar.	CC 38 **Rhythm** as 1 Puls (jetzt)	CC 39 **Rhythm** as 1 Puls (jetzt)	CC 40 **Rhythm** as 1 Puls (jetzt)	CC 41 **Rhythm** as 1 Puls (jetzt)	CC 42 **Rhythm** as 1 Puls (jetzt)	CC 43 **Rhythm** as 1 Puls (jetzt)	CC 44 —
Button 2 Echo throw	CC 45 **Echo throw** held: long dotted-8th echo.	CC 46 **Echo throw** as 1 Puls (jetzt)	CC 47 **Echo throw** as 1 Puls (jetzt)	CC 48 **Echo throw** as 1 Puls (jetzt)	CC 49 **Echo throw** as 1 Puls (jetzt)	CC 50 **Echo throw** as 1 Puls (jetzt)	CC 51 **Echo throw** as 1 Puls (jetzt)	CC 52 —

Mode 2 — Context

	1	2	3	4	5 Progression	6 Drums	7 Bass	8 Pad
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** sine kick, off-beat hat, short clap (as 008).	CC 59 **Bass** off-beat square bass on the chord root.	CC 60 **Pad** 008's pad, minor-9 chords.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Next** next progression (1, 1–4, 1–6, 1–6–4–5), at the next 8-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 —	CC 98 **Drums out** everything but the drums while held.	CC 99 —	CC 100 —

Generated from `lab/harmonie/techno-akkorde-1.strudel` — edit the `@ctl` comments in the track, not this sheet.

Guide

What to listen for

At all knobs 0: which one sits with kick and pad without pulling attention? Which still sounds good after 32 bars?

Live

Turn row 3 slowly: on 2 and 6 it is the echo tail, on 3 the band, on 5 the drive. Button 2 = echo throw.