Launch Control XL 3 — Track 008 — groove techno (two controllers)

Groove techno on F, 140 BPM. Jojo plays the foundation (kick, bass, drums), Jonas the colour (pads, dub chords, melodies) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Jonas' pad button 1 changes the chords, and Jojo's sub and bassline follow.

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Knob | Fader | Button | global (all modes) | unused

Jojo — Foundation (beat + bass)

	1 Kick	2 Sub	3 Bassline	4 Clap	5 Hats	6 Percussion	7 Ride	8 Rumble
Row 1 Brightness	CC 13 **Brightness** dull thump ↔ clicky attack (lpf 300–9000 Hz). Never fully closed.	CC 14 **Brightness** pure sine ↔ a little buzz on top (a triangle an octave up fades in).	CC 15 **Brightness** round and dark ↔ buzzing, squelchy (lpf 150–3000 Hz).	CC 16 **Brightness** soft and far ↔ sharp crack (lpf 1.5–14 kHz).	CC 17 **Brightness** soft hiss ↔ crisp and sharp (lpf 3–16 kHz).	CC 18 **Brightness** woody ↔ metallic (lpf 600–12000 Hz).	CC 19 **Brightness** dark shimmer ↔ bright sizzle (lpf 2.5–16 kHz).	CC 20 **Brightness** deep rumble ↔ more of the kick's body in the tail (lpf 70–1200 Hz).
Row 2 Space	CC 21 **Space** dry and close ↔ in a room (reverb).	CC 22 **Space** dry ↔ a little room (reverb).	CC 23 **Space** dry ↔ a little room (reverb).	CC 24 **Space** dry ↔ far away (reverb + echo).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Space** short rumble ↔ a long dark cloud (reverb never fully off: the reverb is the sound).
Row 3 Character	CC 29 **Drive** tight and clean ↔ distorted, fat.	CC 30 **Length** short blips ↔ long, booming tones.	CC 31 **Groove** off-beats only ↔ extra 16th notes bouncing in between.	CC 32 **Ghost notes** plain ↔ quiet rimshots in between.	CC 33 **Density** off-beats only ↔ all 16ths ↔ + little 32nd rolls.	CC 34 **Density** a hit now and then ↔ the full pattern + extra rimshots.	CC 35 **Swing** straight ↔ swung, lazy (the in-between 16ths come late).	CC 36 **Motion** still ↔ the filter breathes and the rumble echoes in 16ths.
Fader Level	CC 5 **Level** 0 = gone. The 909 kick.	CC 6 **Level** rolling sub, follows Jonas' chords.	CC 7 **Level** off-beat bass, follows Jonas' chords.	CC 8 **Level** clap on 2 and 4. Also the level of Tension's snare roll.	CC 9 **Level** 16th hats. Keep playing in the break.	CC 10 **Level** toms and rimshots. Keep playing in the break.	CC 11 **Level** ride. Keeps playing in the break.	CC 12 **Level** rumble under the kick.
Button 1 Change	CC 37 **Change** next of 8 kick patterns.	CC 38 **Change** next of 8 rolling rhythms.	CC 39 **Change** next of 8 bass lines.	CC 40 **Change** next of 8 clap patterns.	CC 41 **Change** next of 8 accent patterns.	CC 42 **Change** next of 8 tom patterns.	CC 43 **Change** next of 8 ride patterns.	CC 44 **Change** next of 8 rumble rhythms.
Button 2 Moment	CC 45 **Drop out** kick pauses while held.	CC 46 **Slide** every note bends up into its pitch while held.	CC 47 **Octave** one octave up while held.	CC 48 **Roll** snare roll, growing over the bar, while held.	CC 49 **Open** open hats on the off-beats while held.	CC 50 **Fill** a tom run over the bar while held.	CC 51 **Double** double time while held.	CC 52 **Riser** a noise sweep rises over 2 bars while held.

Jonas — Colour (chords + melodies) · column 8 = global

	1 Pad	2 Dub Chords	3 Sequence	4 Lead	5 Answer	6 Pings	7 FX	8 Global
Row 1 Brightness	CC 13 **Brightness** muffled ↔ open and airy (lpf 250–6000 Hz).	CC 14 **Brightness** warm and muffled ↔ bright, glassy (lpf 400–8000 Hz).	CC 15 **Brightness** soft plucks ↔ sharp, metallic (lpf 800–12000 Hz).	CC 16 **Brightness** soft and round ↔ biting (acid squelch) (lpf 250–5000 Hz).	CC 17 **Brightness** hushed ↔ clear (lpf 800–10000 Hz).	CC 18 **Brightness** soft glow ↔ glittering (lpf 2–16 kHz).	CC 19 **Brightness** dark whoosh ↔ bright hiss (lpf 1.5–14 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from the room next door.
Row 2 Space	CC 21 **Space** dry and close ↔ far away in a big room (reverb + echo).	CC 22 **Space** dry ↔ the echoes repeat far into the distance.	CC 23 **Space** dry ↔ far away (reverb + echo).	CC 24 **Space** dry ↔ far away (reverb + echo).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Swell** 0 = held chords. Up = the chord is re-struck on every half bar and breathes in and out.	CC 30 **Length** long ringing chords ↔ short, choppy stabs.	CC 31 **Range** few notes of the loop ↔ every 16th, with octave leaps.	CC 32 **Glide** plain notes ↔ notes bend into their pitch, like a slide.	CC 33 **Voices** 0 = one voice, 0.5 = + a third above, 1 = + a fifth: three-part blips.	CC 34 **Density** a ping now and then (~1 per bar) ↔ a rain of pings (~55 % of the 16ths).	CC 35 **Amount** 0 = only the sweep. Up = noise hits on the one every 4 bars and random zaps on the off-beats.	CC 36 **Tension** build-up: echo grows, filters open, from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 5 **Level** dark pad.	CC 6 **Level** dub chord stabs (same chords as the pad).	CC 7 **Level** hypnotic sequence on the chord.	CC 8 **Level** resonant line on the chord.	CC 9 **Level** counter blips, a short phrase every second bar.	CC 10 **Level** metallic pings.	CC 11 **Level** noise sweeps.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** next of 8 chord progressions, for all.	CC 38 **Change** next of 8 stab rhythms.	CC 39 **Change** next of 8 loops (3, 5 or 7 steps).	CC 40 **Change** next of 8 lines.	CC 41 **Change** next of 8 phrase rhythms (new notes too).	CC 42 **Change** next of 8 random ping patterns.	CC 43 **Change** next of 8 sweep shapes (length and direction).	CC 44 **Chapter** dorian → minor → phrygian, at the next bar.
Button 2 Moment	CC 45 **Freeze** holds the current chord while held, for everybody.	CC 46 **Stab** a chord on every off-beat while held.	CC 47 **Octave** one octave up while held.	CC 48 **Echo throw** long echo on the line while held.	CC 49 **Answer** the phrase plays in every bar while held.	CC 50 **Burst** a rain of pings while held.	CC 51 **Hit** an impact on the one of every bar while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Playing together

Jojo builds the floor: kick first, then sub and hats, then clap, bassline and the groove (percussion, ride). Rumble glues it together under the kick.

Jonas colours it: pad or dub chords first, then the sequence. Lead, answer and pings are for the peaks, FX for the transitions.

The pad's button 1 changes the chords for both players: Jojo's sub and bassline move with it. Pad button 2 (freeze) holds the chord for everybody.

Break: one press takes out kick, sub, bassline, clap and rumble at the next bar; hats, percussion, ride and all of Jonas' sounds keep going. Turn Tension up during the break, press again: everything is back on the one. Then let Tension go.

Every position sounds good

No filter closes completely, and space 0 is dry but never silent. Row 2 at about the middle gives the colour stems their dub echo.