Launch Control XL 3 — Track 009 — cool house (one controller)

Cool, minimal classic house in A minor, 122 BPM: few parts, straight grid, one iconic stab. Jojo plays the foundation (kick, bass, drums, ride), Jonas the colour (pad, stab, riff, acid, Rhodes, voice, dub chord) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Chapter (Jonas, column 8) changes the chords for everybody at the next 4-bar phrase.

One controller: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Shaker / Ride) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages.

Knob | Fader | Button | global (all modes) | unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Kick	2 Atmo	3 Sub	4 Rubber Bass	5 Clap / Snare	6 Hats	7 Rim / Toms	8 Global
Row 1 Brightness	CC 13 **Brightness** 0 = full and punchy ↔ extra click on top (lpf 3–16 kHz).	CC 14 **Brightness** dull whoosh ↔ airy hiss (lpf 1.5–12 kHz).	CC 15 **Brightness** 0 = sine with a few overtones (audible on small speakers) ↔ warm and full.	CC 16 **Brightness** dark and round ↔ a buzzing edge (lpf 250–2500 Hz).	CC 17 **Brightness** warm ↔ sharp crack (lpf 2–12 kHz).	CC 18 **Brightness** soft hiss ↔ crisp and sharp (lpf 4–16 kHz).	CC 19 **Brightness** woody ↔ sharp click (lpf 2–14 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from outside the club.
Row 2 Space	CC 21 **Space** dry and close ↔ in a room (reverb).	CC 22 **Space** dry ↔ far away (reverb + echo).	CC 23 **Space** dry ↔ a little room (reverb).	CC 24 **Space** dry ↔ a little room (reverb).	CC 25 **Space** dry ↔ far away (reverb + echo).	CC 26 **Space** dry ↔ far away (reverb + echo).	CC 27 **Space** dry ↔ far away (reverb + echo).	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 29 **Softness** 0 = punchy 909 kick ↔ 1 = soft, round thump.	CC 30 **Motion** still ↔ the filter breathes and the noise wanders left and right.	CC 31 **Length** long, pumping notes ↔ short, bouncing ones.	CC 32 **Rubber** 0 = plain notes ↔ the filter snaps open on every note (rubbery, “bwop”).	CC 33 **Snare** 0 = 909 clap ↔ clap + snare ↔ 1 = 909 snare.	CC 34 **Density** the pattern as it is ↔ + quiet, scattered 16ths.	CC 35 **Toms** 0 = rim only ↔ + low and mid 909 toms.	CC 36 **Tension** build-up: echo grows, filters open, from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 5 **Level** 0 = gone. Four-on-the-floor kick, tuned to A.	CC 6 **Level** noise that pumps with the kick.	CC 7 **Level** sub on the chord's bass note, follows the chapter.	CC 8 **Level** rubber bass, follows the chapter.	CC 9 **Level** clap on 2 and 4. Also the level of Tension's snare roll.	CC 10 **Level** off-beat open hat. Keeps playing in the break.	CC 11 **Level** rimshot figure. Keeps playing in the break.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 37 **Change** straight → a gap every 4th bar → a gap every 8th bar.	CC 38 **Change** pump → off-beat breath → slow waves.	CC 39 **Change** pump → off-beat → half bars.	CC 40 **Change** off-beat → off-beat with octave → 3-3-2.	CC 41 **Change** 2 and 4 → only 4 (half time) → a little fill every 4th bar.	CC 42 **Change** off-beat → + straight 16ths → closed only.	CC 43 **Change** clave → offbeat pair → two-bar figure.	CC 44 **Chapter** next chords for all, at the next phrase (5-8: chord memory).
Button 2 Moment	CC 45 **Drop out** kick pauses while held.	CC 46 **Riser** a noise sweep rises over 2 bars while held. Keeps playing in the break.	CC 47 **Slide** every note bends up into its pitch while held.	CC 48 **Octave** one octave up while held.	CC 49 **Roll** snare roll, growing over the bar, while held.	CC 50 **Open** open hats on every 8th while held.	CC 51 **Fill** a tom run over the bar while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Pad	2 Stab	3 Riff	4 Acid	5 Rhodes	6 Voice	7 Dub Chord	8 Global
Row 1 Brightness	CC 61 **Brightness** dark and far ↔ open (lpf 0.8–6 kHz).	CC 62 **Brightness** dark, muted stab ↔ open and biting (lpf 0.6–8 kHz).	CC 63 **Brightness** warm, soft touch ↔ open, bright grand (lpf 2.5–18 kHz).	CC 64 **Brightness** closed and dark ↔ open (filter cutoff 200–2500 Hz).	CC 65 **Brightness** mellow ↔ bell-like tine (lpf 1.5–10 kHz).	CC 66 **Brightness** hushed ↔ open, clear voice (lpf 1–8 kHz).	CC 67 **Brightness** deep and muffled ↔ clear (lpf 0.4–4 kHz).	CC 20 **Fog** 0 = clear, up = every filter pulled down to ~6 %: muffled, as if from outside the club.
Row 2 Space	CC 69 **Space** dry ↔ a big hall (reverb + echo).	CC 70 **Space** dry ↔ the echoes repeat into the room.	CC 71 **Space** dry ↔ the echoes repeat into the room.	CC 72 **Space** dry ↔ echoes into the room.	CC 73 **Space** dry ↔ far away (reverb + echo).	CC 74 **Space** dry ↔ far away (reverb + echo).	CC 75 **Space** a short echo ↔ a long tail into the room.	CC 28 **Room** 0 = each sound's own room (row 2), up = everything drowns in reverb.
Row 3 Character	CC 77 **Motion** 0 = still ↔ the filter breathes slowly over 8 bars.	CC 78 **Sound** 0 = synth stab (saw) ↔ both ↔ 1 = M1-style organ stab.	CC 79 **Pedal** 0 = played, damped after each note ↔ 1 = sustain pedal, notes ring on.	CC 80 **Acid** 0 = soft and round ↔ resonant squelch (more resonance and filter envelope).	CC 81 **Length** short chords ↔ held over the bar.	CC 82 **Glide** plain notes ↔ notes bend gently into their pitch (at most a semitone).	CC 83 **Hits** one hit per bar ↔ + a second, quieter hit.	CC 36 **Tension** build-up: echo grows, filters open, from the middle a snare roll (clap fader). 0 = release.
Fader Level	CC 53 **Level** pad on the chapter's chords.	CC 54 **Level** the stab on the chapter's chords.	CC 55 **Level** piano riff.	CC 56 **Level** acid line.	CC 57 **Level** Rhodes chords on the chapter's chords.	CC 58 **Level** the voice.	CC 59 **Level** dub chord, follows the chapter.	CC 12 **Master Level** volume of everything, both controllers. 0 = silence.
Button 1 Change	CC 85 **Change** full chord → only the top (thin, high) → low and wide.	CC 86 **Change** off-beat → syncopated → a two-bar call.	CC 87 **Change** ostinato → answer → 2 riffs that follow the chords.	CC 88 **Change** 16ths → 8ths → two-bar line.	CC 89 **Change** on 1 → on 3-and → 1 + a late answer.	CC 90 **Change** one note → a falling pair → three notes.	CC 91 **Change** on 2-and → on 4-and → every 2nd bar.	CC 44 **Chapter** next chords for all, at the next phrase (5-8: chord memory).
Button 2 Moment	CC 93 **Freeze** holds the current chord while held, for everybody.	CC 94 **Open** the filter opens wide while held.	CC 95 **Octave** one octave up while held.	CC 96 **Accent** every note accented (louder, the filter snaps) while held.	CC 97 **Swell** the chord swells in slowly while held.	CC 98 **Echo throw** long echo on the voice while held.	CC 99 **Throw** the echo repeats much longer while held.	CC 52 **Break / Drop** 1st: beat out. 2nd: all back on the one.

Guide

Playing together

Less is the point: Jojo builds kick, hats, sub and clap and then mostly leaves the patterns alone. Atmo, rim and shaker / ride come and go with the faders.

Jonas: the stab is the hook. Bring it in alone, let it run for 16 bars, work only its brightness. The riff or the acid line is the second voice, rarely all three at once. Pad, Rhodes, voice and dub chord are for the quiet parts.

Chapter changes the chords for both players at the next 4-bar phrase. Chapters 1-4 are voice-led progressions, 5-8 the parallel minor-9 chord memory. Sub, bass and the chords follow; riff, acid and voice keep their melody and only bend a note where it would clash. Pad button 2 (freeze) holds the chord for everybody.

Build-up and drop: Jonas turns Tension up (echo, open filters, snare roll), presses Break at the top: the beat goes out, pad and stab float. Jojo holds the riser (atmo, button 2), Jonas presses Break again: everything is back on the one. Then let Tension go.

Every position sounds good

Space 0 is dry and close, as the track is meant to be; room is a colour you add. No filter closes completely.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.