Launch Control XL 3 — Techno-Pads 1 (lab/harmonie, 008: one pad column, chords + colour)

Columns 1–8 = pad sounds. Button 1 on ANY column = next chord progression, button 2 on ANY column = next colour (7, 9, fourths, fifths). Both switch at the next chord and act on all columns and the bass.

Columns 1 and 2 = Pad and Techno-Pad as they are in 008 (reference). Context in Mode 2: drums, bass.

Knob | Fader | Button | unused

Mode 16 — Pad candidates

	1 Pad (jetzt)	2 Techno (jetzt)	3 Beide	4 Tief	5 Superchor	6 Kalt	7 Gedreht	8 Echo-Pad
Row 1 Brightness	CC 13 **Brightness** dark ↔ open (low-pass, range per column).	CC 14 **Brightness** as 1 Pad (jetzt)	CC 15 **Brightness** as 1 Pad (jetzt)	CC 16 **Brightness** as 1 Pad (jetzt)	CC 17 **Brightness** as 1 Pad (jetzt)	CC 18 **Brightness** as 1 Pad (jetzt)	CC 19 **Brightness** as 1 Pad (jetzt)	CC 20 **Brightness** as 1 Pad (jetzt)
Row 2 Space	CC 21 **Space** a little room ↔ far away (reverb; column 8 also more echo).	CC 22 **Space** as 1 Pad (jetzt)	CC 23 **Space** as 1 Pad (jetzt)	CC 24 **Space** as 1 Pad (jetzt)	CC 25 **Space** as 1 Pad (jetzt)	CC 26 **Space** as 1 Pad (jetzt)	CC 27 **Space** as 1 Pad (jetzt)	CC 28 **Space** as 1 Pad (jetzt)
Row 3 Pump	CC 29 **Pump** 0 = held chords ↔ the kick pumps the chord on every beat.	CC 30 **Pump** as 1 Pad (jetzt)	CC 31 **Pump** as 1 Pad (jetzt)	CC 32 **Pump** as 1 Pad (jetzt)	CC 33 **Pump** as 1 Pad (jetzt)	CC 34 **Pump** as 1 Pad (jetzt)	CC 35 **Pump** as 1 Pad (jetzt)	CC 36 **Pump** as 1 Pad (jetzt)
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Pad (jetzt)	CC 7 **Level** as 1 Pad (jetzt)	CC 8 **Level** as 1 Pad (jetzt)	CC 9 **Level** as 1 Pad (jetzt)	CC 10 **Level** as 1 Pad (jetzt)	CC 11 **Level** as 1 Pad (jetzt)	CC 12 **Level** as 1 Pad (jetzt)
Button 1 Chords	CC 37 **Chords** next progression (8), for all columns and the bass, at the next chord.	CC 38 **Chords** as 1 Pad (jetzt)	CC 39 **Chords** as 1 Pad (jetzt)	CC 40 **Chords** as 1 Pad (jetzt)	CC 41 **Chords** as 1 Pad (jetzt)	CC 42 **Chords** as 1 Pad (jetzt)	CC 43 **Chords** as 1 Pad (jetzt)	CC 44 **Chords** as 1 Pad (jetzt)
Button 2 Colour	CC 45 **Colour** 7 → 9 → fourths → fifths, for all columns, at the next chord.	CC 46 **Colour** as 1 Pad (jetzt)	CC 47 **Colour** as 1 Pad (jetzt)	CC 48 **Colour** as 1 Pad (jetzt)	CC 49 **Colour** as 1 Pad (jetzt)	CC 50 **Colour** as 1 Pad (jetzt)	CC 51 **Colour** as 1 Pad (jetzt)	CC 52 **Colour** as 1 Pad (jetzt)

Mode 2 — Context

	1	2	3	4	5 Harmony	6 Drums	7 Bass	8
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** sine kick, off-beat hat, short clap (as 008).	CC 59 **Bass** off-beat square bass on the chord root.	CC 60 —
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Chords** next progression (same as button 1 above).	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 **Colour** next colour (same as button 2 above).	CC 98 **Drums out** everything but the drums while held.	CC 99 —	CC 100 —

Generated from `lab/harmonie/techno-pads-1.strudel` — edit the `@ctl` comments in the track, not this sheet.

Guide

What to listen for

Which column sounds fullest at all knobs 0 without covering the bass? Which progression still pulls after 32 bars?

Live

Row 3 (Pump) turns a held chord into a pumping one. Button 2 changes the colour of the chord for everyone.