Launch Control XL 3 — Track 009 — house

Happy, jazzy, dry house in A minor, 124 BPM. Jojo plays the rhythm (kick, bass, drums, percussion), Jonas the harmony with the chord progressions (column 1), the keys (column 2), the vibraphone (column 3), the flute (column 4; 5-7 empty for now) and the global column 8.

Every row means the same everywhere: row 1 = brightness, row 2 = space, row 3 = character, fader = level, button 1 = next pattern (at the next bar), button 2 = a moment while held.

Start with all faders down. Nothing sounds until Jonas' master fader (column 8) is up. Chapter (Jonas, column 8) switches between one chord (Vamp) and the progression chosen on Jonas 1 (Progression) at the next 4-bar phrase.

Every Launch Control XL 3 gets this full layout: Mode 1 = Jojo (foundation, columns 1–7; Jojo's column 8 (Tamb / Ride) stays off; Mode 1 sends the same CCs as Mode 16), Mode 2 = Jonas (colour). Column 8 is global on both pages. Two controllers: the control moved last wins.

Knob Fader Button global (all modes) unused

Mode 1 — Jojo: Foundation (beat + bass) · same CCs as Mode 16

	1 Kick	2 Noise Pump	3 Sub	4 Bass	5 Clap	6 Hats / Shaker	7 Congas	8 Global
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright.	CC 14 **Brightness** dull ↔ bright.	CC 15 **Brightness** sine ↔ full.	CC 16 **Brightness** dull ↔ bright.	CC 17 **Brightness** soft ↔ sharp.	CC 18 **Brightness** soft ↔ crisp.	CC 19 **Brightness** woody ↔ crisp.	CC 20 **Fog** clear ↔ muffled (all low-passes down).
Row 2 Space	CC 21 **Space** dry ↔ room.	CC 22 **Space** dry ↔ room.	CC 23 **Space** dry ↔ room.	CC 24 **Space** dry ↔ room.	CC 25 **Space** dry ↔ room.	CC 26 **Space** dry ↔ room.	CC 27 **Space** dry ↔ room.	CC 28 **Thin** full ↔ thin (all high-passes up).
Row 3 Character	CC 29 **Punch** tight ↔ hard.	CC 30 **Motion** still ↔ moving.	CC 31 **Length** long ↔ short.	CC 32 **Sound** FM → M1 organ → analog.	CC 33 **Complexity** plain → rim → double taps.	CC 34 **Hats ↔ Shaker** hats → both → shaker.	CC 35 **Complexity** steady → + ghost notes.	CC 36 **Tension** build-up: echo, reverb, open filters; past half also a snare roll.
Fader Level	CC 5 **Level** four on the floor.	CC 6 **Level** noise that pumps with the kick.	CC 7 **Level** sub on the chord's root.	CC 8 **Level** bass line on the chords.	CC 9 **Level** clap on 2 and 4.	CC 10 **Level** off-beat hat + 16ths.	CC 11 **Level** congas and bongos.	CC 12 **Master** volume of everything.
Button 1 Change	CC 37 **Pattern** 4/4 → gap every 4th bar → every 8th bar.	CC 38 **Pattern** pump → off-beat → 16ths.	CC 39 **Pattern** pump → off-beat → half bars.	CC 40 **Pattern** 7 lines, 3-3-2 first.	CC 41 **Pattern** 2 + 4 → pickup → fill every 4th bar.	CC 42 **Pattern** off-beat → + 16ths → driving.	CC 43 **Pattern** pillow → rolling → latin.	CC 44 **Chapter** Vamp (Am9) ↔ Progression (Chords, column 1).

Button 2 Moment	CC 45 **Drop** kick, pump, sub out while held.	CC 46 **Riser** rising sweep while held.	CC 47 **Octave** up while held.	CC 48 **Octave** up while held.	CC 49 **Roll** snare roll while held.	CC 50 **Open** open hats while held.	CC 51 **Fill** conga run while held.	CC 52 **Break** 1st: kick, pump, sub, bass out. 2nd: all back on the one.

Mode 2 — Jonas: Colour (chords + melodies) · CC + 48

	1 Harmony	2 Keys	3 Vibraphone	4 Flute	5 Brass	6 Strings	7 Guitar	8 Global
Row 1 Brightness	CC 61 **Brightness** dull ↔ bright.	CC 62 **Brightness** dull ↔ bright.	CC 63 **Brightness** dull ↔ bright.	CC 64 **Brightness** dull ↔ bright.	CC 65 **Brightness** dull ↔ bright.	CC 66 **Brightness** dull ↔ bright.	CC 67 **Brightness** dull ↔ bright.	CC 20 **Fog** clear ↔ muffled (all low-passes down).
Row 2 Space	CC 69 **Space** dry ↔ echo + room.	CC 70 **Space** dry ↔ echo + room.	CC 71 **Space** dry ↔ echo + room.	CC 72 **Space** dry ↔ echo + room.	CC 73 **Space** dry ↔ echo + room.	CC 74 **Space** dry ↔ echo + room.	CC 75 **Space** dry ↔ echo + room.	CC 28 **Thin** full ↔ thin (all high-passes up).
Row 3 Character	CC 77 **Strings ↔ B3** strings → both → B3.	CC 78 **Length** short ↔ long.	CC 79 **Complexity** core → figure → fills → doubles.	CC 80 **Complexity** core → + neighbours → + trill.	CC 81 **Complexity** core → + pickups → + extra hits.	CC 82 **Complexity** unison → octave → thirds → celli.	CC 83 **Complexity** line → dead notes → variation → motor + fill.	CC 36 **Tension** build-up: echo, reverb, open filters; past half also a snare roll.
Fader Level	CC 53 **Level** held chords.	CC 54 **Level** piano, Rhodes, organs, mallets.	CC 55 **Level** vibraphone.	CC 56 **Level** flute.	CC 57 **Level** brass section.	CC 58 **Level** string section.	CC 59 **Level** plucked guitar.	CC 12 **Master** volume of everything.
Button 1 Change	CC 85 **Chords** next of 10 (at the next 8 bars).	CC 86 **Pattern** 6 rhythms on Am9 → 5 riffs with own chords.	CC 87 **Pattern** off-beat → tresillo → call echo.	CC 88 **Pattern** 3-3-2 → call + answer → steady 8ths.	CC 89 **Pattern** 9 figures, the sparse ones last.	CC 90 **Pattern** 5 figures.	CC 91 **Pattern** 8 lines.	CC 44 **Chapter** Vamp (Am9) ↔ Progression (Chords, column 1).
Button 2 Moment	CC 93 **Echo throw** long echo while held.	CC 94 **Sound** on: knobs = sound mix, fader = overtones.	CC 95 **Echo throw** long echo while held.	CC 96 **Echo throw** long echo while held.	CC 97 **Lift** section grows while held.	CC 98 **Lift** section grows while held.	CC 99 **Lift** phaser, brighter while held.	CC 52 **Break** 1st: kick, pump, sub, bass out. 2nd: all back on the one.

Guide

Building it up

One layer after the other, not all at once: drums (kick, hats, clap), then bass and sub, then the keys, then percussion (congas, tambourine). Start in Vamp.

Harmony

Button 1 of column 1 picks the progression (at the next 8-bar phrase); it plays when Chapter is Progression. Row 3 fades strings → strings + B3 → B3.

Keys

1:1 from the keys lab (round 19, column 2): brightness, space, length; button 1 = 6 stab rhythms + 5 riffs with their own chords; button 2 = sound: the knobs mix the sound (piano → Rhodes, organ B3 → M1, vibraphone → marimba), the fader sets how strongly the overtones follow the accent.

Break and drop

Jonas presses Break: the whole rhythm goes out at the next bar, only the keys and the high percussion (clap, hats, congas, tambourine) keep playing. Jojo holds the riser (noise pump, button 2). Jonas switches Chapter to Progression and presses Break again: everything is back on the one, now with the progression.

Every position sounds good

All knobs at 0 is dry, close and clear, as the track is meant to be. Space adds room, it does not repair. Every column has its own fader: each layer can be muted on its own.

Status box

The status box at the bottom right of the Strudel page shows chapter, break and each stem's pattern. Its button “als Fenster” opens it as a small window that stays on top (Chrome/Edge).

Playing alone

A run is: build the beat in Mode 1, switch to Mode 2, add colour, use column 8 for the drop. Mode 1 is set up in Components with the same CCs as Mode 16.

Faders are shared hardware: after a mode switch each sound keeps its value until you touch its fader, then it jumps to where the fader physically is. Move faders gently after switching.

Playing together

Both Launch Controls have the full layout and steer the same sounds: whoever moves a control last sets its value, a button press counts from either. Agree who plays which page.