Launch Control XL 3 — Midori 3 (lab/harmonie, 007: Takada-style marimba layers)

Six ways of laying plain marimba figures over each other, in D lydian over 007's context (Mode 2). Button 1 = plain ⟶ wild, row 3 = layers, button 2 = marimba ⟶ toms ⟶ both.

Knob Fader Button unused

Mode 16 — Candidates

	1 Cycles / Canon / Cells	2 Euclid	3 Build-up	4 Bell Pulse	5 Railway Crossing	6 Clapping Music	7	8
Row 1 Brightness	CC 13 **Brightness** soft mallet ↔ bright (low-pass).	CC 14 **Brightness** as 1 Cycles / Canon / Cells	CC 15 **Brightness** as 1 Cycles / Canon / Cells	CC 16 **Brightness** as 1 Cycles / Canon / Cells	CC 17 **Brightness** as 1 Cycles / Canon / Cells	CC 18 **Brightness** as 1 Cycles / Canon / Cells	CC 19 —	CC 20 —
Row 2 Space	CC 21 **Space** room and dotted-8th echo (a little at 0).	CC 22 **Space** as 1 Cycles / Canon / Cells	CC 23 **Space** as 1 Cycles / Canon / Cells	CC 24 **Space** as 1 Cycles / Canon / Cells	CC 25 **Space** as 1 Cycles / Canon / Cells	CC 26 **Space** as 1 Cycles / Canon / Cells	CC 27 —	CC 28 —
Row 3 Character	CC 29 **Layers** 0 = one figure / voice ↔ all of them.	CC 30 **Layers** 0 = one layer ↔ all 4.	CC 31 **Intensity** 0 = the figure alone ↔ up to 7 layers, louder and brighter.	CC 32 **Layers** 0 = bell + line 1 ↔ + line 2 ↔ + line 3.	CC 33 **Crossings** 0 = one bell ↔ 4 bells at different speeds.	CC 34 **Layers** 0 = the pattern alone ↔ + the moving voice ↔ + a low anchor.	CC 35 —	CC 36 —
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Cycles / Canon / Cells	CC 7 **Level** as 1 Cycles / Canon / Cells	CC 8 **Level** as 1 Cycles / Canon / Cells	CC 9 **Level** as 1 Cycles / Canon / Cells	CC 10 **Level** as 1 Cycles / Canon / Cells	CC 11 —	CC 12 —
Button 1 Change	CC 37 **Change** 9 options: 3 cycles ⟶ 3 canons ⟶ 3 cells.	CC 38 **Change** sparse ⟶ middle ⟶ dense.	CC 39 **Change** a new layer every 8 ⟶ 4 ⟶ 2 bars.	CC 40 **Change** interlocked ⟶ line 2 slides ⟶ all slide.	CC 41 **Change** speeds close ⟶ apart ⟶ far apart.	CC 42 **Change** moves every 8 ⟶ 4 ⟶ 2 bars.	CC 43 —	CC 44 —
Button 2 Moment	CC 45 **Toms** press: marimba ⟶ toms (an octave lower) ⟶ both, stays.	CC 46 **Toms** as 1 Cycles / Canon / Cells	CC 47 **Toms** as 1 Cycles / Canon / Cells	CC 48 **Toms** as 1 Cycles / Canon / Cells	CC 49 **Toms** as 1 Cycles / Canon / Cells	CC 50 **Toms** as 1 Cycles / Canon / Cells	CC 51 —	CC 52 —

Mode 2 — Context

	1	2	3	4	5 Progression	6 Heartbeat	7 Drone	8 Pad
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 —	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Heartbeat** 007's soft pulse on D.	CC 59 **Drone** D–A drone, swelling every 2 bars.	CC 60 **Pad** 007's pad, high-passed (less mud).
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Progression** next of 3, at the next 8 bars.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 **Back** previous progression.	CC 98 **Pulse out** the pulse pauses while held.	CC 99 —	CC 100 —

Guide

What to listen for

Railway crossing and Clapping Music: does the shifting rhythm come through? How high can build-up go?