Launch Control XL 3 — Horns Lab 2 (lab/horns, round 2 for 009 column 2: real horn stabs)

Real recordings (VSCO 2 trumpet, Bear Sax baritone, both CC0) against the GM brass section of round 1. Same three stab rhythms on every column.

Mode 2: fader 6 = drums (knob 1 = swing, button 2 = drums out), fader 7 = bass, fader 8 = keys of 009; column 5 button 1 = harmony (one chord ↔ Am9/D9).

Knob | Fader | Button | unused

Mode 16 — Candidates

	1 Brass GM	2 Trumpets	3 Trumpet + bari	4 Bari growl	5	6	7	8
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright over the sound's own range; brighter also plays a little harder (±2 dB).	CC 14 **Brightness** as 1 Brass GM	CC 15 **Brightness** as 1 Brass GM	CC 16 **Brightness** as 1 Brass GM	CC 17 —	CC 18 —	CC 19 —	CC 20 —
Row 2 Space	CC 21 **Space** 0 = dry; a 1/8 echo from the first turn (full at half), the room joins from a third on.	CC 22 **Space** as 1 Brass GM	CC 23 **Space** as 1 Brass GM	CC 24 **Space** as 1 Brass GM	CC 25 —	CC 26 —	CC 27 —	CC 28 —
Row 3 Length	CC 29 **Length** 0 = clipped stabs ↔ hits ring four times longer.	CC 30 **Length** as 1 Brass GM	CC 31 **Length** as 1 Brass GM	CC 32 **Length** as 1 Brass GM	CC 33 —	CC 34 —	CC 35 —	CC 36 —
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Brass GM	CC 7 **Level** as 1 Brass GM	CC 8 **Level** as 1 Brass GM	CC 9 —	CC 10 —	CC 11 —	CC 12 —
Button 1 Change	CC 37 **Change** call + answer → off-beat 16ths → short-short-long, next bar.	CC 38 **Change** as 1 Brass GM	CC 39 **Change** as 1 Brass GM	CC 40 **Change** as 1 Brass GM	CC 41 —	CC 42 —	CC 43 —	CC 44 —
Button 2 Echo throw	CC 45 **Echo throw** held: long dotted-8th echo, the tail rings on.	CC 46 **Echo throw** as 1 Brass GM	CC 47 **Echo throw** as 1 Brass GM	CC 48 **Echo throw** as 1 Brass GM	CC 49 —	CC 50 —	CC 51 —	CC 52 —

Mode 2 — Context

	1	2	3	4	5 Harmony	6 Drums	7 Bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 **Keys** the keys of 009 (Steinway + Rhodes, chain rhythm), to hear the answers.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Harmony** Ein Akkord ↔ Wechsel, at the next 4-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 —	CC 98 **Drums out** horns, keys and bass alone while held.	CC 99 —	CC 100 —

Generated from `lab/horns/horns-lab-2.strudel` — edit the `@ctl` comments in the track, not this sheet.

Guide

What to listen for

Do the real trumpets sound like house horns (and not quacky)? Which rhythm answers the keys?

Harmony

Ein Akkord: Am9 (stab E G B). Wechsel: Am9 2 bars, D9 2 bars (stab E F♯ A), as in track 009.