Launch Control XL 3 — House Keys Lab 2 (lab/keys/old, round 2 for 009)

Rhythm on one chord: columns 1-7 are seven rhythm ideas for the keys, column 8 the plain riffs for progressions. Pull up one fader at a time; button 1 = next of its three patterns.

The sound is set once in Mode 2: faders 1-4 mix grand, Rhodes, organ stab and vibraphone as layers; every rhythm column plays through that mix. Mode 2 column 5 button 1 = harmony (one chord → two chords → three old progressions).

"⍰ LC groß" in the status box opens the dashboard: every control, its value and the pattern that plays.

Knob Fader Button unused

Mode 16 — Rhythms

	1 Threes	2 Stutter	3 Off-beat	4 Call	5 Syncopes	6 Gaps	7 Left hand	8 Basic
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (lpf 1.5–14 kHz).	CC 14 **Brightness** as 1 Threes	CC 15 **Brightness** as 1 Threes	CC 16 **Brightness** as 1 Threes	CC 17 **Brightness** as 1 Threes	CC 18 **Brightness** as 1 Threes	CC 19 **Brightness** as 1 Threes	CC 20 **Brightness** as 1 Threes
Row 2 Space	CC 21 **Space** 0 = dry ↔ a room.	CC 22 **Space** as 1 Threes	CC 23 **Space** as 1 Threes	CC 24 **Space** as 1 Threes	CC 25 **Space** as 1 Threes	CC 26 **Space** as 1 Threes	CC 27 **Space** as 1 Threes	CC 28 **Space** as 1 Threes
Row 3 Length	CC 29 **Length** 0 = short stabs ↔ hits ring four times longer.	CC 30 **Length** as 1 Threes	CC 31 **Length** as 1 Threes	CC 32 **Length** as 1 Threes	CC 33 **Length** as 1 Threes	CC 34 **Length** as 1 Threes	CC 35 **Length** as 1 Threes	CC 36 **Length** as 1 Threes
Fader Level	CC 5 **Level** dotted hits: 3 against 4, across the bar line.	CC 6 **Level** short bursts of 16ths, then silence.	CC 7 **Level** chords between the kicks, the organ-house pump.	CC 8 **Level** one chord, answered by single top notes.	CC 9 **Level** only off-16ths: never on the beat.	CC 10 **Level** few hits, lots of space, pushes before the one.	CC 11 **Level** low root and upper chord alternate (gospel left hand).	CC 12 **Level** the plain riffs of the old piano lab, for progressions.
Button 1 Change	CC 37 **Change** threes → threes + ghost → fives.	CC 38 **Change** burst → four + two → two-bar burst.	CC 39 **Change** off-beat → ghost before → ghost around.	CC 40 **Change** wide → close → long + run.	CC 41 **Change** chain → pairs → two-bar chain.	CC 42 **Change** two hits → push → held pair.	CC 43 **Change** bounce → swing → busy.	CC 44 **Change** 3-3-2 → off-beat → hymn.
Button 2 Moment	CC 45 **Double** the pattern runs twice as fast while held.	CC 46 **Double** as 1 Threes	CC 47 **Double** as 1 Threes	CC 48 **Double** as 1 Threes	CC 49 **Double** as 1 Threes	CC 50 **Double** as 1 Threes	CC 51 **Double** as 1 Threes	CC 52 **Double** as 1 Threes

Mode 2 — Sound + global

	1 Grand	2 Rhodes	3 Organ stab	4 Vibraphone	5 Harmony	6 Drums	7 Bass	8
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 **Grand** layer level: dry grand piano.	CC 54 **Rhodes** layer level: warm electric piano.	CC 55 **Organ stab** layer level: short, clicky organ.	CC 56 **Vibraphone** layer level: soft, jazzy mallets.	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 —
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Harmony** one chord → two → Happy → Deep → Italo, at the next 4 bars.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 —	CC 98 **Drums out** keys and bass alone while held.	CC 99 —	CC 100 —

Guide

Why one chord

When the chords move, the ear follows the harmony and hears a song; a busy rhythm on top makes it disco. In house the chord stands still and the rhythm, the filter and the layers do the work. So columns 1-7 are meant for harmony 1 (one chord) or 2 (two chords).

Progressions

Harmony 3-5 are the progressions of the old piano lab (Happy, Deep, Italo). They work with plain rhythms: column 8 (3-3-2, off-beat, hymn).

Sound layers

Mode 2, faders 1-4: grand, Rhodes, organ stab, vibraphone. Two layers at once (e.g. grand + organ) play the same notes and become one thicker instrument, like the M1 piano of the 90s.

Patterns

The pattern under button 1 shows x = chord, g = ghost chord, t / u = single top notes, L = low root, h = upper half, - = held, . = rest. Patterns shorter than a bar (3, 5, 6 steps) run across the bar line: that is the polyrhythm.