Launch Control XL 3 — Sample Lab 1 (lab/samples, round 1 for 009 column 4: recorded phrases from the listening list)

Plays the candidates of hoerliste.md in time: one category per column, button 1 = next candidate, row 3 = start point in the file. Not fitted to key or tempo yet: pick by ear, fitting comes next.

Mode 2: fader 6 = drums (knob 1 = swing, button 2 = drums out), fader 7 = bass, fader 8 = keys of 009; column 5 button 1 = harmony.

Knob Fader Button unused

Mode 16 — Candidates

	1 Horn stabs	2 Sax	3 Trumpet	4 Guitar	5 Flute	6 Voice	7 Rhodes / organ	8 Vinyl / strings
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (low-pass).	CC 14 **Brightness** as 1 Horn stabs	CC 15 **Brightness** as 1 Horn stabs	CC 16 **Brightness** as 1 Horn stabs	CC 17 **Brightness** as 1 Horn stabs	CC 18 **Brightness** as 1 Horn stabs	CC 19 **Brightness** as 1 Horn stabs	CC 20 **Brightness** as 1 Horn stabs
Row 2 Space	CC 21 **Space** 0 = dry; echo, then room.	CC 22 **Space** as 1 Horn stabs	CC 23 **Space** as 1 Horn stabs	CC 24 **Space** as 1 Horn stabs	CC 25 **Space** as 1 Horn stabs	CC 26 **Space** as 1 Horn stabs	CC 27 **Space** as 1 Horn stabs	CC 28 **Space** as 1 Horn stabs
Row 3 Start	CC 29 **Start** where in the file playback starts (0 = beginning, 1 = near the end).	CC 30 **Start** as 1 Horn stabs	CC 31 **Start** as 1 Horn stabs	CC 32 **Start** as 1 Horn stabs	CC 33 **Start** as 1 Horn stabs	CC 34 **Start** as 1 Horn stabs	CC 35 **Start** as 1 Horn stabs	CC 36 **Start** as 1 Horn stabs
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Horn stabs	CC 7 **Level** as 1 Horn stabs	CC 8 **Level** as 1 Horn stabs	CC 9 **Level** as 1 Horn stabs	CC 10 **Level** as 1 Horn stabs	CC 11 **Level** as 1 Horn stabs	CC 12 **Level** as 1 Horn stabs
Button 1 Next	CC 37 **Next** next candidate of this category (see the dashboard), next bar.	CC 38 **Next** as 1 Horn stabs	CC 39 **Next** as 1 Horn stabs	CC 40 **Next** as 1 Horn stabs	CC 41 **Next** as 1 Horn stabs	CC 42 **Next** as 1 Horn stabs	CC 43 **Next** as 1 Horn stabs	CC 44 **Next** as 1 Horn stabs
Button 2 Echo throw	CC 45 **Echo throw** held: long dotted-8th echo, the tail rings on.	CC 46 **Echo throw** as 1 Horn stabs	CC 47 **Echo throw** as 1 Horn stabs	CC 48 **Echo throw** as 1 Horn stabs	CC 49 **Echo throw** as 1 Horn stabs	CC 50 **Echo throw** as 1 Horn stabs	CC 51 **Echo throw** as 1 Horn stabs	CC 52 **Echo throw** as 1 Horn stabs

Mode 2 — Context

	1	2	3	4	5 Harmony	6 Drums	7 Bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 **Keys** the keys of 009 (Steinway + Rhodes, chain rhythm), to hear the answers.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Harmony** Ein Akkord ↔ Wechsel, at the next 4-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 —	CC 98 **Drums out** samples, keys and bass alone while held.	CC 99 —	CC 100 —

Guide

What to listen for

Which recordings have the right feel (real, warm, groovy)? Note the column and name (dashboard) of each favourite.

Not yet fitted

Phrases play at their own tempo and key; a clash is expected. The fit (cutting, pitch) comes after you pick.