Launch Control XL 3 — Einwurf 1 (lab/einwurf, 009: rare recorded interjections on phrase points)

Columns 1–3 voices (pickup into the phrase), 4–8 instrument gestures (on the 1 of the phrase). Each occurrence takes the next sample.

Row 3 = how often: button only / every 16 / every 8 / every 4 bars. Button 1 = now (next pickup / next bar).

Knob | Fader | Button | unused

Mode 16 — Candidates

	1 Shouts	2 Yeah yeah	3 Crowd	4 Flute trill	5 Flute run	6 Zither gliss	7 Trombone fall	8 Cuica
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (low-pass).	CC 14 **Brightness** as 1 Shouts	CC 15 **Brightness** as 1 Shouts	CC 16 **Brightness** as 1 Shouts	CC 17 **Brightness** as 1 Shouts	CC 18 **Brightness** as 1 Shouts	CC 19 **Brightness** as 1 Shouts	CC 20 **Brightness** as 1 Shouts
Row 2 Space	CC 21 **Space** echo and room (a little at 0).	CC 22 **Space** as 1 Shouts	CC 23 **Space** as 1 Shouts	CC 24 **Space** as 1 Shouts	CC 25 **Space** as 1 Shouts	CC 26 **Space** as 1 Shouts	CC 27 **Space** as 1 Shouts	CC 28 **Space** as 1 Shouts
Row 3 How often	CC 29 **How often** button only · every 16 · every 8 · every 4 bars.	CC 30 **How often** as 1 Shouts	CC 31 **How often** as 1 Shouts	CC 32 **How often** as 1 Shouts	CC 33 **How often** as 1 Shouts	CC 34 **How often** as 1 Shouts	CC 35 **How often** as 1 Shouts	CC 36 **How often** as 1 Shouts
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Shouts	CC 7 **Level** as 1 Shouts	CC 8 **Level** as 1 Shouts	CC 9 **Level** as 1 Shouts	CC 10 **Level** as 1 Shouts	CC 11 **Level** as 1 Shouts	CC 12 **Level** as 1 Shouts
Button 1 Now	CC 37 **Now** at the next “and” of beat 4.	CC 38 **Now** as 1 Shouts	CC 39 **Now** as 1 Shouts	CC 40 **Now** on the 1 of the next bar.	CC 41 **Now** as 4 Flute trill	CC 42 **Now** as 4 Flute trill	CC 43 **Now** as 4 Flute trill	CC 44 **Now** as 4 Flute trill
Button 2 Echo throw	CC 45 **Echo throw** held: long dotted-8th echo.	CC 46 **Echo throw** as 1 Shouts	CC 47 **Echo throw** as 1 Shouts	CC 48 **Echo throw** as 1 Shouts	CC 49 **Echo throw** as 1 Shouts	CC 50 **Echo throw** as 1 Shouts	CC 51 **Echo throw** as 1 Shouts	CC 52 **Echo throw** as 1 Shouts

Mode 2 — Context

	1	2	3	4	5 Progression	6 Drums	7 Bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 **Keys** the keys of 009, following the progression.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Progression** next progression, at the next 8-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 —	CC 98 **Drums out** everything but the drums while held.	CC 99 —	CC 100 —

Guide

What to listen for

Which interjections are a highlight and stay one after the third time? Too rare / too often?

Harmony

Mode 2 column 5 button 1 cycles the progression; the trombone falls from the chord's root.