Launch Control XL 3 — Komplexität 1 (lab/blaeser, 009 Jonas 5: eight proposals for the complexity knob)

Every column = Jonas 5 brass; the six figures on button 1; only row 3 (complexity) differs from column to column.

Row 3 at 0 = the plain figure everywhere; turn it slowly up and compare.

Knob Fader Button unused

Mode 16 — Candidates

	1 More hits	2 Melody	3 Phrase end	4 Articulation	5 Syncopation	6 Call + answer	7 Harmony	8 Combined
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (low-pass 0.9–8 kHz).	CC 14 **Brightness** as 1 More hits	CC 15 **Brightness** as 1 More hits	CC 16 **Brightness** as 1 More hits	CC 17 **Brightness** as 1 More hits	CC 18 **Brightness** as 1 More hits	CC 19 **Brightness** as 1 More hits	CC 20 **Brightness** as 1 More hits
Row 2 Space	CC 21 **Space** room at 0 ↔ hall and dotted-8th echo.	CC 22 **Space** as 1 More hits	CC 23 **Space** as 1 More hits	CC 24 **Space** as 1 More hits	CC 25 **Space** as 1 More hits	CC 26 **Space** as 1 More hits	CC 27 **Space** as 1 More hits	CC 28 **Space** as 1 More hits
Row 3 Complexity	CC 29 **More hits** core → + pickups and answers → + small extra hits.	CC 30 **Melody** one note → every 2nd hit lower → a contour → + passing notes.	CC 31 **Phrase end** none → pickup run into bar 1 → + bar 4 → shout fill in bar 8.	CC 32 **Articulation** plain → accents → + scoops → + shake and a fall at the phrase end.	CC 33 **Syncopation** on the grid → long notes early → all early → + stop-time gaps.	CC 34 **Call + answer** trumpets alone → horns answer → in harmony → + an answer an octave up.	CC 35 **Harmony** unison → octaves → triads → four-part with 9ths.	CC 36 **Combined** melody → + phrase-end fills → + articulation.
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 More hits	CC 7 **Level** as 1 More hits	CC 8 **Level** as 1 More hits	CC 9 **Level** as 1 More hits	CC 10 **Level** as 1 More hits	CC 11 **Level** as 1 More hits	CC 12 **Level** as 1 More hits
Button 1 Figure	CC 37 **Figure** push → 3-3-2 → shout → double push → 3-3-2 long → swell + push, next bar.	CC 38 **Figure** as 1 More hits	CC 39 **Figure** as 1 More hits	CC 40 **Figure** as 1 More hits	CC 41 **Figure** as 1 More hits	CC 42 **Figure** as 1 More hits	CC 43 **Figure** as 1 More hits	CC 44 **Figure** as 1 More hits
Button 2 Lift (held)	CC 45 **Lift** held: the section grows over 2 bars; back over 1 bar after.	CC 46 **Lift** as 1 More hits	CC 47 **Lift** as 1 More hits	CC 48 **Lift** as 1 More hits	CC 49 **Lift** as 1 More hits	CC 50 **Lift** as 1 More hits	CC 51 **Lift** as 1 More hits	CC 52 **Lift** as 1 More hits

Mode 2 — Context

	1	2	3	4	5 Progression	6 Drums	7 Bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 **Keys** the keys of 009, following the progression.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Next** next progression (all 21), at the next 8-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 **Previous** previous progression, at the next 8-bar phrase.	CC 98 **Drums out** everything but the drums while held.	CC 99 —	CC 100 —

Guide

What to listen for

Which knob makes the brass more interesting without getting busy? Which feels like a real lift?

Live

Button 2 held = lift (voices, brightness, +3 dB) as in the track.