Launch Control XL 3 — Melodie 4 (lab/melodie, 009 Jonas 4/5: wind phrases with build-up, flute melody from real flute notes)

Columns 1–4: recorded wind phrases; row 3 = build-up: 1 per 8 bars → call + answer → every 2 bars → back to back.

Columns 5–6: a playful flute melody from real flute notes on the chord tones; row 3 = playful (neighbour notes, trill).

Knob | Fader | Button | unused

Mode 16 — Candidates

	1 Trumpet	2 Tenor sax	3 Trumpet ↔ sax	4 Flute phrases	5 Flute melody	6 Flute higher	7	8
Row 1 Brightness	CC 13 **Brightness** dull ↔ bright (low-pass).	CC 14 **Brightness** as 1 Trumpet	CC 15 **Brightness** as 1 Trumpet	CC 16 **Brightness** as 1 Trumpet	CC 17 **Brightness** as 1 Trumpet	CC 18 **Brightness** as 1 Trumpet	CC 19 —	CC 20 —
Row 2 Space	CC 21 **Space** echo and room (a little at 0).	CC 22 **Space** as 1 Trumpet	CC 23 **Space** as 1 Trumpet	CC 24 **Space** as 1 Trumpet	CC 25 **Space** as 1 Trumpet	CC 26 **Space** as 1 Trumpet	CC 27 —	CC 28 —
Row 3 Build-up / Playful	CC 29 **Build-up** 1 phrase per 8 bars → call + answer → every 2 bars → back to back (livelier phrases).	CC 30 **Build-up** as 1 Trumpet	CC 31 **Build-up** as 1 Trumpet	CC 32 **Build-up** as 1 Trumpet	CC 33 **Playful** core motif → + neighbour notes → + a short trill.	CC 34 **Playful** as 5 Flute melody	CC 35 —	CC 36 —
Fader Level	CC 5 **Level** 0 = off.	CC 6 **Level** as 1 Trumpet	CC 7 **Level** as 1 Trumpet	CC 8 **Level** as 1 Trumpet	CC 9 **Level** as 1 Trumpet	CC 10 **Level** as 1 Trumpet	CC 11 —	CC 12 —
Button 1 Phrase / Motif	CC 37 **Phrase** which phrase starts, from the next 8-bar phrase; the others follow in order.	CC 38 **Phrase** as 1 Trumpet	CC 39 **Phrase** as 1 Trumpet	CC 40 **Phrase** as 1 Trumpet	CC 41 **Motif** hopping → call and answer → turn.	CC 42 **Motif** as 5 Flute melody	CC 43 —	CC 44 —
Button 2 Echo throw	CC 45 **Echo throw** held: long dotted-8th echo.	CC 46 **Echo throw** as 1 Trumpet	CC 47 **Echo throw** as 1 Trumpet	CC 48 **Echo throw** as 1 Trumpet	CC 49 **Echo throw** as 1 Trumpet	CC 50 **Echo throw** as 1 Trumpet	CC 51 —	CC 52 —

Mode 2 — Context

	1	2	3	4	5 Progression	6 Drums	7 Bass	8 Keys
Row 1	CC 61 —	CC 62 —	CC 63 —	CC 64 —	CC 65 —	CC 66 **Swing** 50 % straight ↔ 70 %; 55–58 % = house.	CC 67 —	CC 68 —
Row 2	CC 69 —	CC 70 —	CC 71 —	CC 72 —	CC 73 —	CC 74 —	CC 75 —	CC 76 —
Row 3	CC 77 —	CC 78 —	CC 79 —	CC 80 —	CC 81 —	CC 82 —	CC 83 —	CC 84 —
Fader Level	CC 53 —	CC 54 —	CC 55 —	CC 56 —	CC 57 —	CC 58 **Drums** 909 kick, off-beat hat, clap, shaker.	CC 59 **Bass** off-beat bass on the chord root.	CC 60 **Keys** the keys of 009, following the progression.
Buttons 1	CC 85 —	CC 86 —	CC 87 —	CC 88 —	CC 89 **Next** next progression (all 21), at the next 8-bar phrase.	CC 90 —	CC 91 —	CC 92 —
Buttons 2	CC 93 —	CC 94 —	CC 95 —	CC 96 —	CC 97 **Previous** previous progression, at the next 8-bar phrase.	CC 98 **Drums out** everything but the drums while held.	CC 99 —	CC 100 —

Guide

What to listen for

Does the build-up turn interjections into a melody? Which step carries a party? Flute: playful but simple enough?

Harmony

Mode 2 column 5 cycles the progression; phrases with F♯ / F skip the progressions they clash with, the flute follows the chords.