Dated:

DATA COMMUNICATION:

Data communication is defined as a process in which more than one computer transfers information, instructions to each other and for sharing resources.

Components of Data communication:

A communication is madeup of the following components;

· Message:

A message is a piece of information that is to be transmitted from one person to another. It could be a text file, an audiofile, videofileetc

sender:

It is simply a device that sends data messages. It can be a computer, mobile, telephone etc.

c. Reciever:

- It is a device that recieves messages. It can be a computer, telephone workstation etc.
- · Transmission Medium / communication channels:
 - Communication channels are the medium that connect two or more workstations. Workstations can be connected by either wired media or wireless media.
- · Set_of rules (Protocol):

When someone sends the data [The sender), it should be understandable to the reciever also otherwise it is meaningless. For example, son a sends a message to Huzaifa. If son a writes in english and Huzaifa didn't understand english, then the conversation is meaningless.

<i>(</i>)	(
Date	<u>d:</u>					
		Protocols				
#Hordi	1	and the second second	GJU W.	- 4416		(
62.44	sender	Message)		Reciever		(
						(
		1	1			(
		Transmition Me	dium	12- 2-11-13	slint to take	•
Tharafa	- Historia	La Laborato Marca Later	- 1		Consider à	-
nurefore	there are	some set of rule. nnected to the inte	s (protoc	ob)that is	followed by	
every a	impuler con	nnected to the inte	ernet ar	nd they a	re;	· .
· TOD TE	anition	2	1 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2 2	<i>I</i> '	1. 1 n (A)	_`
It is mon	arminiosioi	Control Protocol): ·	J J.	THE PROPERTY OF	(
and read	completing t	dividing messages	<u>into pac</u>	ckets on th	le source computer	_(
and reas	serribung (the recieved packet	t at the	destination	on or recipient	<u>'</u>
the cou	· IL also mo	ake sure that par	ckets ho	ave the in	formation about	
chould	he re acces	message data, the	<u>destina</u>	tion of t	he message dato	L_(
correctly	to the	mbled, and ehecks	if the r	riussages r	ias been sent	
whering	U UE S	pecific destination).		<u> </u>	-
IP / Inter	rnet Protoc	701).	1	از این این ایال	<u> المراد المراب الم</u>	(
			addroci	of the	actio tion	
compute	r en that	for handling the c each packet is s	ant to	of the a	estination	
compose	1 30 1101	MCIT PULPEL 13 S	selli 10	its proper	aestination.	
VPNI	Virtual P	rivate Network).		<u> </u>	· I det I hadaa	
Udoa	10 VPN c	NANACE WELWOOLKS	2 4 4 5000	though	(- Val II)	
the	define un	hanges your IP our Location to no	address	, The onl	que address	
100	refile go	of wallon to m	ework.	BY USI	ng VPN User	
COM	easily re	ep their online	activity	private	and secure	¥
<u> </u>	any aat	a'fishers or ha	cker ar	ound th	e globe.	
	*- 10 HL	the second of the second	1 12	, r , j. 1	THE CONTRACTOR	
		matelia Li	J and	hard John	Jan L. B. Grahav, s	
				<u>/il ,</u>	r pi glub 1, 1.	
		•				

Dated:
· Type of Data communication:
The data communication is divided into three types:
The part of the second of the
1 Simplex Communication:
It is one-way communication or we can say that unidirectional
communication in which one device only sends data and devices
uses their entire capacity in transmission. For example, lot,
entering data using a key board, listing music using a speaker, etc.
2 Half Duplex Communication:
It is a two-way communication or we can say that It is a
bidirectional communication in which both the devices can send
and recieve data but not at the same time. When one device is
sending data then another device is only recieving and viceversa.
For example, walkie-talkie
in in a short of the bull of a short of the
Full-Duplex Communication:
It is a two-way communication or we can say that it is a
bidirectional communication in which both the devices can send
and recieve data at the same time. For example, mobile phones
landlines etc.
Communication channels:
Communication Channels are the medium that connects two or more
workstations. The transmission medium can be grouped in
two categories;
-

Czuided Media
Vngvided Media

Dated:	•
	_
· (Juided Media:	2
In this transmission medium, the physical link is created using wires	
Or cables between two or more devices and then the data is	8
transmitted using these cables in term of signals.	-
- Porexample	-
· Twisted Pair Cable De Malanant M. Villenge Ding	4
· Coaxial cable	
- optical fibre cable.	4
- Unquided Media:	
The unguided transmission media is a transmission mode in which	
the cianale are proported from one device to another device	
wirelessly, signals can wave though the air, water, or vaccum. It	
wirelessly signals can wave though the air, water, or vaccum. It is generally used to transmit signals in all directions. Unguided	
Media is further divided into various parts suchas;	^
The state of the s	
· Microwave	-
· Radiowave	-
· Infrared	
· prijenten	-

Popular Communication Media

Communication between computing devices is handled over two types of paths: parallel and serial. These terms refer to the manner in which signals are transferred with respect to each other. In the case of parallel communication, several signals are transferred at the same time, each on a separate "line." Such a technique is capable of transferring data rapidly but requires a relatively complex communication path. Examples include a computer's internal bus where multiple wires are used to allow large blocks of data and other signals to be transferred simultaneously.

In contrast, serial communication is based on transferring signals one after the other over a single line. Thus serial communication requires a simpler data path than parallel communication, which is the reason for its popularity. USB and FireWire, which offer relatively high-speed data transfer over short distances of only a few meters, are examples of serial communication systems. For slightly longer distances (within a home or office building), serial communication over Ethernet connections (Section 4.1), either by wire or radio broadcast, are popular.

For communication over greater distances, traditional voice telephone lines dominated the personal computer arena for many years. These communication paths, consisting of a single wire over which tones are transferred one after the other, are inherently serial systems. The transfer of digital data over these lines accomplished by first converting bit patterns into audible tones by means of a modem (short for modulator-demodulator), transferring these tones serially over the telephone system, and then converting the tones back into bits by another modem at the destination.

For faster long-distance communication over traditional telephone lines, telephone companies offer a service known as DSL (Digital Subscriber Line), which takes advantage of the fact that existing telephone lines are capable of handling a wider frequency range than that used by traditional voice communication. More precisely, DSL uses frequencies above the audible range to transfer digital data while leaving the lower frequency spectrum for voice communication. Although DSL has been highly successful, telephone companies are rapidly upgrading their systems to fiber-optic lines, which support digital communication more readily than traditional telephone lines.

Other technologies that compete with DSL and fiber optics include cable, as used in cable television systems, and satellite links via high-frequency radio broadcast.

Communication Rates

The rate at which bits are transferred from one computing component to another is measured in bits per second (bps). Common units include Kbps (kilo-bps, equal to one thousand bps), Mbps (mega-bps, equal to one million bps), and Gbps (giga-bps, equal to one billion bps). (Note the distinction between bits and bytes—that is, 8 Kbps is equal to 1 KB per second. In abbreviations, a lowercase b usually means bit whereas an uppercase B means byte.)

For short distance communication, USB and FireWire provide transfer rates of several hundred Mbps, which is sufficient for most multimedia applications.

2.5 Communicating with Other Devices

99

This, combined with their convenience and relatively low cost, is why they are popular for communication between home computers and local peripherals such as printers, external disk drives, and cameras.

By combining multiplexing (the encoding or interweaving of data so that a single communication path serves the purpose of multiple paths) and data compression techniques, traditional voice telephone systems were able to support transfer rates of 57.6 Kbps, which falls short of the needs of today's multimedia and Internet applications, such as YouTube and Facebook. To play MP3 music recordings requires a transfer rate of about 64 Kbps, and to play even low quality video clips requires transfer rates measured in units of Mbps. This is why alternatives such as DSL, cable, and satellite links, which provide transfer rates well into the Mbps range, have replaced traditional audio telephone systems. (For example, DSL offers transfer rates on the order of 54 Mbps.)

The maximum rate available in a particular setting depends on the type of the communication path and the technology used in its implementation. This maximum rate is often loosely equated to the communication path's bandwidth, although the term bandwidth also has connotations of capacity rather than transfer rate. That is, to say that a communication path has a high bandwidth (or provides broadband service) means that the communication path has the ability to transfer bits at a high rate as well as the capacity to carry large amounts of information simultaneously.