

Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

Search

Categories

A->Z

System Core

Analog

Timers

Connectivity

CAN

I2C1

I2C2

SPI1

SPI2

USART1

USART2

USART3


USB

Computing

Pinout view

System view

The diagram shows the pinout of an STM32F103C8Tx LQFP48 package. The pins are arranged in four rows around the central chip. The top row includes VDD, VSS, PB9, PB8, BOOT0, PB7, PB6, PB5, PB4, PB3, PA15, and PA14. The right row includes VDD, VSS, PA13, PA12, PA11, PA10, PA9, PA8, PB15, PB14, PB13, and PB12. The bottom row includes PA3, PA4, PA5, PA6, PA7, PB0, PB1, PB2, I2C_SCL, I2C_SDA, VSS, and VDD. The left row includes VBAT, PC13, PC14, PC15, PD0, PD1, NRST, VSSA, VDDA, PA0, PA1, and PA2. Various pins are highlighted in green (PA14, PA13, PA12, PA11, PA10, PA9, PA8, PA7, PA6, PA5, PA4, PA3, PA2, PA1, PA0, PD0, PD1, PB0, PB1, PB2, I2C_SCL, I2C_SDA, PB15, PB14, PB13, PB12, PB9, PB8, PB7, PB6, PB5, PB4, PB3, PB2, PB1, PB0, NRST, VSSA, VDDA, VSS, VBAT, PC13, PC14, PC15, BOOT0, and I2C1). The chip is labeled STM32F103C8Tx LQFP48.



 Pinout view

 **System view**

Middleware

System Core

DMA

GPIO 

NVIC 

RCC 

SYS 

Analog

Timers

TIM3 

Connectivity

I2C2 

Computing

Pinout & Configuration

Clock Configuration

Software Packs

Pinout



Categories

A->Z

System Core >

Analog >

Timers >

Connectivity >

CAN

I2C1

☒ I2C2

SPI1

SPI2

USART1

USART2

☐ USART3

USB

Computing >

I2C2 Mode and Configuration

Mode

I2C I2C

Configuration

Reset Configuration

☒ NVIC Settings☒ DMA Settings☒ GPIO Settings☒ Parameter Settings☒ User Constants

Configure the below parameters :

Search (Ctrl+F)



Master Features

I2C Speed Mode

Standard Mode

I2C Clock Speed (Hz)

100000

Slave Features

Clock No Stretch Mode

Disabled

Primary Address Len...

7-bit

Dual Address Ackno...

Disabled

Primary slave address

0

General Call address...

Disabled

TIM3 Mode and Configuration

Mode

Slave Mode Disable 

Trigger Source Disable 

☒ Internal Clock

Channel1 Disable 

Channel2 Disable 

Configuration

Reset Configuration

 NVIC Settings

 DMA Settings

 Parameter Settings

 User Constants

Configure the below parameters :





Counter Settings

Prescaler (PSC - 16 ... 7199

Counter Mode Up

Counter Period (Aut... 4999

Internal Clock Divisi... No Division

TIM3 Mode and Configuration

Mode

Slave Mode Disable 

Trigger Source Disable 

☒ Internal Clock

Channel1 Disable 

Channel2 Disable 

Configuration

Reset Configuration

 NVIC Settings

 DMA Settings

 Parameter Settings

 User Constants

NVIC Interrupt Table	Enabled	Preemption Priority	Sub P
TIM3 global interrupt	☒	0	0

