Class BTraceUtils.Sys.VM

java.lang.Object com.sun.btrace.BTraceUtils.Sys.VM

Enclosing class:

BTraceUtils.Sys

public static class $\mathtt{BTraceUtils.Sys.VM}$ extends java.lang.Object

Constructor Summary

Constructors

Constructor and Description

VM()

Method Summary

All Methods Static Methods	Concrete Methods
Modifier and Type	Method and Description
static java.lang.String	bootClassPath() Returns the boot class path that is used by the bootstrap class loader to search for class files.
static java.lang.String	ClassPath() Returns the Java class path that is used by the system class loader to search for class files.
static long	currentThreadCpuTime() Returns the total CPU time for the current thread in nanoseconds.
static long	CurrentThreadUserTime() Returns the CPU time that the current thread has executed in user mode in nanoseconds.
static long	daemonThreadCount() Returns the current number of <u>live</u> daemon threads.

2015/5/31 13:00

static boolean		isBootClassPathSupported() Tests if the Java virtual machine supports the boot class path mechanism used by the bootstrap class loader to search for class files.
static java.lang.Str	ing	libraryPath() Returns the Java library path.
static long		peakThreadCount () Returns the peak live thread count since the Java virtual machine started or peak was reset.
static void 打	印" VM输入参数列表 "	<pre>printVmArguments() Prints VM input arguments list.</pre>
static long		processCPUTime() Returns the CPU time used by the process on which the Java virtual machine is running in nanoseconds.
static double		<pre>systemLoadAverage()</pre>
返回最近一分钟	中的"系统负载平均值"	Returns the system load average for the last minute
static long		threadCount() Returns the current number of live threads including both daemon and non-daemon threads.
static long		totalStartedThreadCount() Returns the total number of threads created and also started since the Java virtual machine started.
static java.util.Lis	t <java.lang.string></java.lang.string>	vmArguments() Returns the input arguments passed to the Java virtual machine which does not include the arguments to the main method.
static long		vmStartTime() Returns the start time of the Java virtual machine in milliseconds. 返回JVM的启动时间(ms
static long		vmUptime() Returns the uptime of the Java virtual machine in milliseconds. 返回JVM的运行时间(ms)
static java.lang.Str	ing	vmVersion() Returns the Java virtual machine implementation version. 返回JVM的实现版本

2