






QEMU (Linux-1)



```
route: ioctl 0x890c failed: No such process
Removing default gateway for Ethernet interface ..... [FAILED]
shutting down Ethernet interface eth0 ..... [ OK ]
shutting down loopback interface lo ..... [ OK ]
bringing up loopback interface lo ..... [ OK ]
bringing up Ethernet interface eth0 ..... [ OK ]
set up default gateway ..... [ OK ]
# ifconfig
eth0      Link encap:Ethernet  HWaddr 50:93:4C:01:AD:00
          inet addr:172.16.0.10  Bcast:172.16.255.255  Mask:255.255.0.0
          UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
          RX packets:81 errors:0 dropped:0 overruns:0 frame:0
          TX packets:164 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:16476 (16.0 KiB)  TX bytes:52808 (51.5 KiB)

lo        Link encap:Local Loopback
          inet addr:127.0.0.1  Mask:255.0.0.0
          UP LOOPBACK RUNNING  MTU:16436  Metric:1
          RX packets:0 errors:0 dropped:0 overruns:0 frame:0
          TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:0
          RX bytes:0 (0.0 B)  TX bytes:0 (0.0 B)
```

#

Server Manager ▶ Dashboard

Manage Tools View Help

Dashboard

Local Server

All Servers

File and Storage

Network and Sharing Center

Network Connections

Network and Internet > Network Connections

Search Network Connections

Organize Disable this network device Diagnose this connection Rename this connection

Ethernet Properties

Networking

Co

Th

Internet Protocol Version 4 (TCP/IPv4) Properties

General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address: 172 . 16 . 0 . 20

Subnet mask: 255 . 255 . 0 . 0

Default gateway: 172 . 16 . 0 . 1

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server: . . .

Alternate DNS server: . . .

☐ Validate settings upon exit

Advanced...

OK

Cancel

1 item

Hide

9/2/2026 10:50 AM

10:59 AM

Add Roles and Features Wizard

Installation progress

DESTINATION SERVER
server2016

- Before You Begin
- Installation Type
- Server Selection
- Server Roles
- Features
- Web Server Role (IIS)
- Role Services
- Confirmation
- Results**

View installation progress



Feature installation



Installation succeeded on server2016.

Web Server (IIS)

- Management Tools
 - IIS Management Console
- Web Server
 - Common HTTP Features
 - Default Document
 - Directory Browsing
 - HTTP Errors
 - Static Content
 - Health and Diagnostics
 - HTTP Logging



You can close this wizard without interrupting running tasks. View task progress or open this page again by clicking Notifications in the command bar, and then Task Details.

[Export configuration settings](#)

- < Previous
- Next >
- Close
- Cancel

Hide

Events
Performance
BPA results

Events
Services
Performance
BPA results

General

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address: 8 . 8 . 8 . 8

Subnet mask: 255 . 0 . 0 . 0

Default gateway: 8 . 0 . 0 . 1

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server:

Alternate DNS server:

☐ Validate settings upon exit

Advanced...

OK

Cancel

Add Roles and Features Wizard

Installation progress

- Before You Begin
- Installation Type
- Server Selection
- Server Roles
- Features
- DNS Server
- Confirmation
- Results**

View installation progress

i Starting installation

DNS Server

Remote Server Administration Tools

Role Administration Tools

DNS Server Tools

Export configuration settings

DESTINATION SERVER
server2016

< Previous

Next >

Install

Cancel

Hide

	BPA results	Performance BPA results	
--	-------------	----------------------------	--

DNS Manager

File Action View Help

DNS

- SERVER2016
 - Forward Lookup Zones
 - Reverse Lookup Zones
 - Trust Points
 - Conditional Forwarders

Name	Type	Status	DNSSEC Status
com	Standard Primary	Running	Not Signed

Events
Services
Performance
BPA results

Events
Performance
BPA results

Hide

DNS Manager

File Action View Help

DNS

- SERVER2016
 - Forward Lookup Zones
 - com
 - Reverse L
 - Trust Poi
 - Condition

Name	Type	Status	DNSSEC Status
com	Standard Primary	Running	Not Signed

New DNS Domain

Type the new DNS domain name:

hotstar

OK Cancel

Events
Services
Performance
BPA results

Events
Performance
BPA results

Hide

DNS Manager

File Action View Help

DNS

- SERVER2016
 - Forward Lookup Zones
 - com
 - Reverse L
 - Trust Poi
 - Condition

Name	Type	Status	DNSSEC Status	Key Master
com	Standard Primary	Running	Not Signed	

New DNS Domain

Type the new DNS domain name:

OK Cancel

Events
Services
Performance
BPA results

Events
Performance
BPA results

Hide

DNS Manager

File Action View Help

DNS

- SERVER2016
 - Forward Lookup Zones
 - com
 - hotstar
 - netflix
 - Reverse Lookup Zones
 - Trust Points
 - Conditional Forwarders

Name

- hotstar
- netflix
- (same a
- (same a

New Host

Name (uses parent domain name if blank):

www

Fully qualified domain name (FQDN):

www.hotstar.com.

IP address:

172.16.0.10

☐ Create associated pointer (PTR) record

Add Host Cancel

Events
Services
Performance
BPA results

Events
Performance
BPA results

DNS Manager

File Action View Help

DNS

SERVER2016

Forward Lookup Zones

com

hotstar

netflix

Reverse Lookup Zones

Trust Points

Conditional Forwarders

Name

hotstar

netflix

(same as)

(same as)

New Host

Name (uses parent domain name if blank):

Fully qualified domain name (FQDN):

IP address:

DNS

The host record www.netflix.com was successfully created.

OK

Events

Services

Performance

BPA results

Events

Performance

BPA results

My Documents

My Computer

My Network Places

Recycle Bin

Internet Explorer

Cisco ASDM-I...

Old Java ASDM

PuTTY

Tftpd32

Network Connections

Local Area Connection Properties

Internet Protocol (TCP/IP) Properties

General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address: 50 . 0 . 0 . 10

Subnet mask: 255 . 0 . 0 . 0

Default gateway: 50 . 0 . 0 . 1

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server: 8 . 8 . 8 . 8

Alternate DNS server: . . .

Advanced...

OK

Cancel

Hello World! This file is located in /home/httpd



IIS Windows Server - Windows Internet Explorer



File Edit View Favorites Tools Help

Favorites Suggested Sites Web Slice Gallery

IIS Windows Server



Windows Server

Internet Information Services

Welcome

Bienvenue

Tervetuloa

ようこそ

Benvenuto

歓迎

Bienvenido

Hoş geldiniz

ברוכים הבאים

Welkom

Bem-vindo



Καλώς
ορίσαστε

Välkommen

환영합니다

Добро
пожаловать

Üdvözöljük

Vítejte

Microsoft

Willkommen

Velkommen



مرحبا 欢迎

Witamy

Done



IIS Windows Server - ...

Internet

100% 12:37 PM