

R1

```
*Aug 24 10:38:49.912: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to do
wn
*Aug 24 10:38:49.921: %LINK-3-UPDOWN: Interface Ethernet0/3, changed state to do
wn
*Aug 24 10:38:50.912: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
2, changed state to down
*Aug 24 10:38:50.921: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
3, changed state to down
R1#
R1#
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#int e0/0
R1(config-if)#ip add 10.0.0.1 255.0.0.0
R1(config-if)#no sh
R1(config-if)#exit
R1(config)#
R1(config)#
R1(config)#int e0/1
R1(config-if)#ip add 20.0.0.1 255.0.0.0
R1(config-if)#no sh
R1(config-if)#exit
R1(config)#
R1(config)#ip route 30.0.0.0
*Aug 24 10:43:39.541: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R1(config)#ip route 30.0.0.0 255.0.0.0 20.0.0.2
R1(config)#ip route 40.0.0.0 255.0.0.0 20.0.0.2
R1(config)#
R1(config)#
R1(config)#
R1(config)#
```



R2

```
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#int e0/0
R2(config-if)#ip add 20.0.0.2 255.0.0.0
R2(config-if)#no sh
R2(config-if)#exit
R2(config)#
R2(config)#int e0/1
R2(config-if)#ip add 30.0.0.1 255.0.0.0
R2(config-if)#no sh
R2(config-if)#exit
R2(config)#
R2(config)#
R2(config)#ip route 10.0.0.0 255.0.0.0 20.0.0.1
R2(config)#ip route 40.0.0.0 255.0.0.0 30.0.0.2
R2(config)#
R2(config)#
```



R1

R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#

R1#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP

D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area

N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2

E1 - OSPF external type 1, E2 - OSPF external type 2

i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2

ia - IS-IS inter area, * - candidate default, U - per-user static route

o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP

a - application route

+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C 10.0.0.0/8 is directly connected, Ethernet0/0
L 10.0.0.1/32 is directly connected, Ethernet0/0
20.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C 20.0.0.0/8 is directly connected, Ethernet0/1
L 20.0.0.1/32 is directly connected, Ethernet0/1
S 30.0.0.0/8 [1/0] via 20.0.0.2
S 40.0.0.0/8 [1/0] via 20.0.0.2

R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#



R2

R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#

R2#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

S 10.0.0.0/8 [1/0] via 20.0.0.1
20.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C 20.0.0.0/8 is directly connected, Ethernet0/0
L 20.0.0.2/32 is directly connected, Ethernet0/0
30.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C 30.0.0.0/8 is directly connected, Ethernet0/1
L 30.0.0.1/32 is directly connected, Ethernet0/1
S 40.0.0.0/8 [1/0] via 30.0.0.2

R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#
R2#

—  

Gateway of last resort is not set

[illegible]

Windows XP desktop environment with several open windows:

- cmd.exe**: Command Prompt window showing the path `C:\WINDOWS\system32\cmd.exe`.
- Network Connections**: Network and Sharing Center window showing a list of network connections on the left and details on the right. The details pane shows "No connectivity" and "1.0 Gbps".
- Local Area Connection Properties**: Properties window for the selected network connection, showing tabs for General, Advanced, and Sharing.
- Internet Protocol (TCP/IP) Properties**: Properties window for the selected network connection, showing the General tab with the following settings:
 - ☐ Obtain an IP address automatically
 - ☒ Use the following IP address:
 - IP address: 10 . 0 . 0 . 10
 - Subnet mask: 255 . 0 . 0 . 0
 - Default gateway: 10 . 0 . 0 . 1
 - ☐ Obtain DNS server address automatically
 - ☒ Use the following DNS server addresses:
 - Preferred DNS server: . . .
 - Alternate DNS server: . . .

My I
Mi
C
C:
My
My
My
Re
Intern
Explo
Cisco
ASDM
Old Java
PuTTY
TFTP
Tftpd32

C:\WINDOWS\system32\cmd.exe

Network Connections

File Edit View Favorites Tools Advanced Help

Back Forward Search Folders

Address Local Area Connection Properties

Network Tasks

- Create connection
- Set up office network
- Change Firewall
- Disable device
- Repair connection
- Rename connection
- View status of connection
- Change connection

Other Places

- Control Panel
- My Network Places
- My Documents
- My Computer

Details

Local Area Connection

LAN or High-Speed Internet

Internet Protocol (TCP/IP) Properties

General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address: 40 . 0 . 0 . 10

Subnet mask: 255 . 0 . 0 . 0

Default gateway: 40 . 0 . 0 . 1

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:

Preferred DNS server: . . .

Alternate DNS server: . . .

Advanced...

OK Cancel

Local Area Connection Status


00:39:03

1.0 Gbps

Received

0

Close



```
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ncpa.cpl

C:\Documents and Settings\user>route print
=====
Interface List
0x1 ..... MS TCP Loopback interface
0x2 ...50 cf cb 01 aa 00 ..... Intel(R) PRO/1000 MT Network Connection - Packet
Scheduler Miniport
=====
Active Routes:
Network Destination        Netmask          Gateway          Interface        Metric
0.0.0.0                    0.0.0.0          10.0.0.1         10.0.0.10        10
10.0.0.0                   255.0.0.0        10.0.0.10        10.0.0.10        10
10.0.0.10                  255.255.255.255  127.0.0.1        127.0.0.1        10
10.255.255.255             255.255.255.255  10.0.0.10        10.0.0.10        10
127.0.0.0                  255.0.0.0        127.0.0.1        127.0.0.1        1
224.0.0.0                  240.0.0.0        10.0.0.10        10.0.0.10        10
255.255.255.255           255.255.255.255  10.0.0.10        10.0.0.10        1
Default Gateway:          10.0.0.1
=====
Persistent Routes:
None

C:\Documents and Settings\user>ping 40.0.0.10

Pinging 40.0.0.10 with 32 bytes of data:

Reply from 40.0.0.10: bytes=32 time=3ms TTL=125
Reply from 40.0.0.10: bytes=32 time=2ms TTL=125
Reply from 40.0.0.10: bytes=32 time=1ms TTL=125
Reply from 40.0.0.10: bytes=32 time=2ms TTL=125

Ping statistics for 40.0.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 3ms, Average = 2ms

C:\Documents and Settings\user>_
```