

terminal

VPC-1 × VPC-2 × R1 × R2 × Win × VPC-4 ×

failed

Bad command: "pipe2 failed". Use ? for help.

VPC-1>

VPC-1> ip dhcp

DDORA IP 50.0.0.2/8 GW 50.0.0.1

VPC-1> █

Terminal

VPC-1 × VPC-2 × R1 × R2 × Win × VPC-4 ×

```
VPC-2> ip dhcp  
DDORA IP 50.0.0.3/8 GW 50.0.0.1
```

```
VPC-2> █
```

Terminal

VPC-1 x VPC-2 x R1 x R2 x Win x VPC-4 x

% Invalid input detected at '^' marker.

R1#sh ip dhcp binding

Bindings from all pools not associated with VRF:

IP address	Client-ID/ Hardware address/ User name	Lease expiration	Type
------------	--	------------------	------

R1#conf t

Enter configuration commands, one per line. End with CNTL/Z.

R1(config)#ip dhcp pool sales dept

R1(dhcp-config)#network 192.168.2.0 255.255.255.0

R1(dhcp-config)#default-router 192.168.2.1

R1(dhcp-config)#dns-server 8.8.8.8

R1(dhcp-config)#lease 22 0 0

R1(dhcp-config)#lease 22 0 0

R1(dhcp-config)#lease 22 0 0

R1(config)#ex

% Ambiguous command: "ex"

R1(config)#exit

R1#

*Sep 2 02:58:28.091: %SYS-5-CONFIG_I: Configured from console by console

R1#sh ip dhcp binding

Bindings from all pools not associated with VRF:

IP address	Client-ID/ Hardware address/ User name	Lease expiration	Type
50.0.0.2	0100.5079.6668.b9	Sep 26 2026 08:20 AM	Automatic

R1#

```
Terminal
VPC-1 * VPC-2 * R1 * R2 * Win * VPC-4 *
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip dhcp pool sales dept
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
R1(dhcp-config)#default-router 192.168.2.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 22 0 0
R1(dhcp-config)#lease 22 0 0
R1(dhcp-config)#lease 22 0 0
R1(config)#ex
% Ambiguous command: "ex"
R1(config)#exit
R1#
*Sep 2 02:58:28.091: %SYS-5-CONFIG_I: Configured from console by console
R1#sh ip dhcp binding
Bindings from all pools not associated with VRF:
IP address      Client-ID/      Lease expiration      Type
                Hardware address/
                User name
50.0.0.2        0100.5079.6668.b9      Sep 26 2026 08:20 AM      Automatic
R1#sh ip dhcp binding
Bindings from all pools not associated with VRF:
IP address      Client-ID/      Lease expiration      Type
                Hardware address/
                User name
50.0.0.2        0100.5079.6668.b9      Sep 26 2026 08:20 AM      Automatic
50.0.0.3        0100.5079.6668.ba      Sep 26 2026 08:37 AM      Automatic
192.168.2.51    0150.ae34.0911.00      Sep 02 2026 08:41 AM      Automatic
R1#
```

C:\WINDOWS\system32\cmd.exe

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

Connection-specific DNS Suffix	:	:	:	:	:	:
Autoconfiguration IP Address	:	:	:	:	:	169.254.97.86
Subnet Mask	:	:	:	:	:	255.255.0.0
Default Gateway	:	:	:	:	:	:

C:\Documents and Settings\user>ipconfig

Windows IP Configuration

Ethernet adapter Local Area Connection:

Connection-specific DNS Suffix	:	:	:	:	:	:
IP Address	:	:	:	:	:	192.168.2.101
Subnet Mask	:	:	:	:	:	255.255.255.0
Default Gateway	:	:	:	:	:	192.168.2.1

C:\Documents and Settings\user>

```
Terminal
VPC-1 x R1 x R2 x Win x VPC-4 x

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-4>
VPC-4> ipdhcp
Bad command: "ipdhcp". Use ? for help.

VPC-4> ip dhcp
DDORA IP 192.168.2.102/24 GW 192.168.2.1

VPC-4> █
```