

# AIM: Implementation of DSR Routing Protocol



```
mvlu@IT-09: ~
..."
    (file "dsr_sim.tcl" line 1)
mvlu@IT-09:~$ nano dsr_sim.tcl
mvlu@IT-09:~$ cat dsr_sim.tcl
set ns [new Simulator]
$ns node-config -adhocRouting DSR \
-llType LL \
-macType Mac/802_11 \
-ifqType Queue/DropTail/PriQueue \
-ifqLen 50 \
-antType Antenna/OmniAntenna \
-propType Propagation/TwoRayGround \
-phystype Phy/WirelessPhy \
-channelType Channel/WirelessChannel \
-topoInstance $topo \
-agentTrace ON \
-routerTrace ON \
-macTrace OFF
mvlu@IT-09:~$ nano dsr_sim.tcl
mvlu@IT-09:~$ ls
 aodv_out.nam   aodv_sim.tcl   dsr.tr          dsr_sim.tcl              nam_1.15-6.dsc         nam_error.txt
 aodv_out.tr    dsr.nam        dsr_practical   nam_1.15-6.debian.tar.xz  nam_1.15.orig.tar.gz  'nano aodv_sim.tcl'
mvlu@IT-09:~$ nam dsr_out.nam
nam:
mvlu@IT-09:~$ nam dsr.nam
nam:
mvlu@IT-09:~$ wc -l dsr.nam
0 dsr.nam
mvlu@IT-09:~$ head -20 dsr.nam
mvlu@IT-09:~$ nano dsr_sim.tcl
mvlu@IT-09:~$ rm -f dsr.nam dsr.tr
mvlu@IT-09:~$ ns dsr_sim.tcl
warning: Please use -channel as shown in tcl/ex/wireless-mitf.tcl
can't read "phyType_": no such variable
    while executing
"$node add-interface $chan $propInstance_ $llType_ $macType_  $ifqType_ $ifqlen_ $phyType_ $antType_ $topoInstance_  $inerrProc_ $outerrProc_ $FECProc_"
    (procedure "_o3" line 83)
    (Simulator create-wireless-node line 83)
    invoked from within
"_o3 create-wireless-node"
    ("eval" body line 1)
    invoked from within
```



```
mvlu@IT-09: ~
 GNU nano 7.2                                    dsr_sim.tcl
set ns [new Simulator]

set tracefd [open dsr.tr w]
set namfd [open dsr.nam w]

set topo [new Topography]
$topo load_flatgrid 500 500

set god_ [create-god 3]

$ns trace-all $tracefd
$ns namtrace-all-wireless $namfd 500 500

set chan_1_ [new Channel/WirelessChannel]


$ns node-config \
    -adhocRouting DSR \
    -llType LL \
    -macType Mac/802_11 \
    -ifqType Queue/DropTail/PriQueue \
    -ifqLen 50 \
    -antType Antenna/OmniAntenna \
    -propType Propagation/TwoRayGround \
    -phyType Phy/WirelessPhy \
    -channel $chan_1_ \
    -topoInstance $topo \
    -agentTrace ON \
    -routerTrace ON \
    -macTrace OFF


set n0 [$ns node]
set n1 [$ns node]
set n2 [$ns node]

$n0 random-motion 0
$n1 random-motion 0
$n2 random-motion 0

^G Help          ^O Write Out     ^W Where Is      ^K Cut           ^T Execute       ^C Location      M-U Undo         M-A Set Mark     M-] To Bracket   M-Q Previous
^X Exit          ^R Read File     ^\ Replace       ^U Paste         ^J Justify       ^/ Go To Line    M-E Redo         M-6 Copy         ^Q Where Was     M-W Next
```

HARIPRASAD VISHWAKARMA
T127
TYCS




HARIPRASAD VISHWAKARMA
T127
TYCS