

CSA1509-Cloud computing and Big Data Analytics

Name : S.Harish

Reg.no: 192524413

EXP 13 : Create a Virtual Machine with 1 CPU, 2GB RAM and 15GB storage disk using a Type 2 Virtualization Software.

Aim:

To create a VM with:


- No of processor : 1
- Memory : 2 GB
- Hard disk : 15 GB

Steps:


1. Download VMware software and install it as Type-2 Hypervisor.
2. Download Ubuntu or tiny os as ISO image file.
3. In VMware workstation → Create new VM
4. Do the configuration based on given conditions.
5. Created a virtual Machine .
6. Launch the VM.

Implementation:


1. Download and open VMware software.



2. Create a new VM




Name it anything→click on next→Adjust the size of disk → change the option to first and then click on next.




Click on Finish to Launch .

3.VM is created



4. we can customize the configuration of hard disk while creating VM and can add additional hard disk later if needed



The image shows a screenshot of the 'Add Hardware Wizard' dialog box, specifically the 'Specify Disk Capacity' step. The dialog has a title bar with the text 'Add Hardware Wizard' and a close button (X). The main content area is titled 'Specify Disk Capacity' with the subtitle 'How large do you want this disk to be?'. Below this, there is a text input field for 'Maximum disk size (GB):' with the value '15.0' and a spin button. A line of text below the input field states 'Recommended size for Ubuntu: 20 GB'. There are two radio button options: 'Allocate all disk space now.' (which is unchecked) and 'Store virtual disk as a single file' (which is selected). Below the 'Allocate all disk space now.' option, there is a paragraph of text: 'Allocating the full capacity can enhance performance but requires all of the physical disk space to be available right now. If you do not allocate all the space now, the virtual disk starts small and grows as you add data to it.' Below the 'Store virtual disk as a single file' option, there is a paragraph of text: 'Splitting the disk makes it easier to move the virtual machine to another computer but may reduce performance with very large disks.' At the bottom of the dialog, there are three buttons: '< Back', 'Next >', and 'Cancel'.

Add Hardware Wizard

Specify Disk Capacity
How large do you want this disk to be?

Maximum disk size (GB): 15.0

Recommended size for Ubuntu: 20 GB


☐ Allocate all disk space now.
Allocating the full capacity can enhance performance but requires all of the physical disk space to be available right now. If you do not allocate all the space now, the virtual disk starts small and grows as you add data to it.

☒ Store virtual disk as a single file


☐ Split virtual disk into multiple files
Splitting the disk makes it easier to move the virtual machine to another computer but may reduce performance with very large disks.

< Back Next > Cancel

5. Double click on the processor and set it to given configuration



7. Double click on the ram to customize the desired storage



8.VM with given configuration

