

Topology:



Allowing PC1 (Before):



Router 0 Configurations:

```
Router0
                                                                                             \Box
                                                                                                     X
 Physical Config CLI Attributes
                                         IOS Command Line Interface
  Router#
  %SYS-5-CONFIG_I: Configured from console by console
  Router#configure terminal
  Enter configuration commands, one per line. End with {\tt CNTL/Z.}
  Router(config) #interface FastEthernet0/0
  Router(config-if) #no shutdown
  Router(config-if)#
  %LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
  %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
  Router(config-if) #exit
  Router(config) #interface Serial2/0
  Router(config-if)#
  %LINK-5-CHANGED: Interface Serial2/0, changed state to up
  %LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up
  Router(config-if) #access-list 100 permit tcp host 192.168.1.2 host 192.168.3.2 eq 21
  Router(config) #int se2/0
  Router(config-if) #ip access-group 100 out
  Router(config-if) #exit
  Router(config)#
```

Denying PC1 (After):

```
₱PC1

                                                                       \times
            Config
                    Desktop
                               Programming
  Command Prompt
                                                                              Χ
  Packet Tracer PC Command Line 1.0 C:\>ping 192.168.3.3
  Pinging 192.168.3.3 with 32 bytes of data:
  Request timed out.
  Reply from 192.168.3.3: bytes=32 time=1ms TTL=126
  Reply from 192.168.3.3: bytes=32 time=1ms TTL=126
  Reply from 192.168.3.3: bytes=32 time=1ms TTL=126
  Ping statistics for 192.168.3.3:
  Packets: Sent = 4, Received = 3, Lost = 1 (25% loss), Approximate round trip times in milli-seconds:
       Minimum = lms, Maximum = lms, Average = lms
  C:\>ftp 192.168.3.2
  Trying to connect...192.168.3.2
  %Error opening ftp://192.168.3.2/ (Timed out)
   (Disconnecting from ftp server)
```

Allowing PC0:

```
PC0
                                                                                Physical
             Config Desktop Programming
                                                   Attributes
  Command Prompt
                                                                                        Χ
  Packet Tracer PC Command Line 1.0 C:\>ping 192.168.3.2
  Pinging 192.168.3.2 with 32 bytes of data:
  Request timed out.
  Reply from 192.168.3.2: bytes=32 time=2ms TTL=126 Reply from 192.168.3.2: bytes=32 time=1ms TTL=126 Reply from 192.168.3.2: bytes=32 time=3ms TTL=126
  Ping statistics for 192.168.3.2:
      Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
  Approximate round trip times in milli-seconds:
       Minimum = 1ms, Maximum = 3ms, Average = 2ms
  C:\>ftp 192.168.3.2
Trying to connect...192.168.3.2
  Connected to 192.168.3.2
220- Welcome to PT Ftp server
  Username:cisco
  331- Username ok, need password
  Password:
  230- Logged in
  (passive mode On)
   ftp>
```