

Contents

1 May 21, 2026, Thursday	1
1.1 We have optimised the fluorescence (0.5%)	2
1.2 We have optimised the yield (Electroformation at 2 volts 10 Hz with spacer).	2
1.3 TODO Measure the thickness of spacer.	2
1.4 TODO Make another spacer with PDMS.	2
1.5 TODO Electroform DOPC GUVs.	2
1.6 TODO Electroform DOPC-PS 50% - Chol 5% GUVs. Make 200 ul of solution	2
1.7 TODO Electroform DOPC-PS 25% - Chol 0% GUVs. Make 200 ul of solution.	2
1.8 TODO Electroform DOPC-F GUVs - Make 100 ul of solution.	2
1.9 How long are the GUVs stable for in time over days?	2
1.10 How to optimise the shape of GUVs (avoid threads and sticking things)	2
1.11 Maximum pressure? (Is bursting pressure independent of size/shape?)	2
1.12 How much time can we aspirate vesicle for below the maximum pressure?	2
1.13 How does the Maximum pressure vary with constituents? (DOPC, DOPC/PS, DOPC/PS/Chol)	2
1.14 Matlab Calculation of Aspiration versus tension.	2
1.15 Image Analysis in Fiji/MATLAB	2
1.16 Matlab calculation of Volume change and area change.	2

1 May 21, 2026, Thursday

We did electroformation of 5%-Chol,25%-PS,70% DOPC, 0.5% LissRhod-PE. We dipped it in Sucrose 0.24M for 15 minutes before starting electroformation. We cleaned ITOs and spacer with Pure IPA and Pure Ethanol. Then we started electroformation at 2 Vpp sine wave 10 Hz, with the spacer of thickness 1 mm (?). After one hour, we poured 100 ul of GUV solution into 1 ml of Glucose 0.26M We picked 10 ul of that diluted solution and poured it into vessel chamber with 800 ul of media (Glucose 0.26 M) We aspirated with 8 um sized pipette.

- 1.1 We have optimised the fluorescence (0.5%)
- 1.2 We have optimised the yield (Electroformation at 2 volts 10 Hz with spacer).
- 1.3 TODO Measure the thickness of spacer.
- 1.4 TODO Make another spacer with PDMS.
- 1.5 TODO Electroform DOPC GUVs.
- 1.6 TODO Electroform DOPC-PS 50% - Chol 5% GUVs. Make 200 ul of solution
- 1.7 TODO Electroform DOPC-PS 25% - Chol 0% GUVs. Make 200 ul of solution.
- 1.8 TODO Electroform DOPC-F GUVs - Make 100 ul of solution.
- 1.9 How long are the GUVs stable for in time over days?
- 1.10 How to optimise the shape of GUVs (avoid threads and sticking things)
- 1.11 Maximum pressure? (Is bursting pressure independent of size/shape?)
- 1.12 How much time can we aspirate vesicle for below the maximum pressure?
- 1.13 How does the Maximum pressure vary with constituents? (DOPC, DOPC/PS, DOPC/PS/Chol)
- 1.14 Matlab Calculation of Aspiration versus tension.
- 1.15 Image Analysis in Fiji/MATLAB
- 1.16 Matlab calculation of Volume change and area change.

```
import numpy as np
print("Hello,world")
```

```
##### Let's make 90% charged DOTAP-DOPC (Positive, non-fluorescent)
Chemicals = ['DOPS','DOPC','LissRhod-PE', 'Cholesterol', 'NBD-DOTAP']
Concentrations = [2.5,2.5,0.05,2.5,0.01]; # In chloroform
MixtureVolumes = [20,150,0,0,0]; # in microliters
```

```

Molecular_Weights = [809.518,785.593,1300.712,386.65,710.34]

# Number of Weights in mixture
Weights = np.multiply(MixtureVolumes, Concentrations)
# Percentage of moles in mixture
WeightPercentages = np.array(Weights) / np.sum(Weights) * 100

Moles = np.array(Weights)/np.array(Molecular_Weights)
MolePercentages = np.array(Moles) / np.sum(Moles) *100
np.set_printoptions(suppress=True, precision=5)

print('Moles')
print(Moles)
print('Weights')
print(Weights)
# Percentage of moles in mixture
print('weight Percentages')
print(np.round(WeightPercentages,2))
print('Mole Percentages')
print(np.round(MolePercentages,2))

```