

Updating license server and licenses

Technical Support FAQ

Category: Technical Services->Licensing->Wibu Lizenzserver

Programs: Allplan 2021
Allplan 2020
Allplan 2019
Allplan 2018
Allplan 2017
Allplan 2016

Document ID: 20160527114300

Internet: <https://connect.allplan.com/en/faqid/20160527114300.html>

Question:

How to update the license server and the licenses?

Answer:

Allplan 2016: Before you do anything, make sure Allplan 2016-1-4 or later is running on all clients.

Allplan 2017 and higher: Check the version of the license server as described below and update the licenses.

1. Updating the license server

Check the version of your installed license server on the server. Starting with the license server version 2016-1-4, the detailed version status (Build-ID) is displayed directly in the lower left corner of the License Settings program.

The latest version 1.1196.xxx.xxx should be displayed here. If an older Build ID is displayed, then you still have an older license server in use. In any case, please update your license server. Download the software for the license server from **Allplan Connect** - license server version 2021 or from the following link.

<https://webdrive.allplan.com/index.php/s/4LrjrymoxESzC6p>

The package is in the folder

/Allplan/Lizenzserver/2021/

Start the new **License Server Setup** on the server or computer you use as the license server. Right-click the *.exe file and select 'Run as administrator' on the shortcut menu.

- Click **Install**.
- Click **Exit**.

If you have not yet installed the license server or if you have not switched to Allplan 2016 or higher until now, you can find detailed step-by-step instructions at

<https://connect.allplan.com/en/faqid/20150618084450.html>

2. Updating the licenses

Update the licenses at the license server as follows:

- Start the **License Settings** program on the server.
- Click **License activation** on the left. Then click the license you want to update so that this license is highlighted in blue.
- As you can see, the 'Update license' function is now available.
- Click **Update license**.
- If your license includes configurations for several seats, you must update each license separately.

Note: When updating the license it can be that you will receive a higher version of the license as the version of Allplan you are using. The license is downward compatible and can be used until Allplan 2016.

Allplan GmbH and affiliated sales organizations not assume any responsibility or liability for the reliability and usefulness of the articles offered and any information provided. You assume sole responsibility for use of the articles offered and the information provided. Terms and conditions of license of Allplan GmbH and / or the general terms and conditions of the sales organizations rendering the service apply.

© 2020 Allplan GmbH. All rights reserved.