

- Step 1
- Choose launch template
- Step 2
- Choose instance launch options
- Step 3 - optional
- Integrate with other services
- Step 4 - optional
- Configure group size and scaling
- Step 5 - optional
- Add notifications
- Step 6 - optional
- Add tags
- Step 7
- Review

Review

Step 1: Choose launch template

Edit

Group details

Auto Scaling group name

MediCore-ASG

Launch template

MediCore-Web-LT

Version

Default

Description

Launch template for Auto Scaling Group

Step 2: Choose instance launch options

Edit

Network

VPC

vpc-0240d2b3afd9ce2b9

Availability Zones and subnets

Availability Zone	Subnet	Subnet CIDR range
euw2-az2 (eu-west-2a)	subnet-08180ff691ddc0b9b	10.0.128.0/20
euw2-az3 (eu-west-2b)	subnet-0ee8b9b42bcc0d43d	10.0.144.0/20

Availability Zone distribution

Balanced best effort

Capacity Reservation preference

Preference	Capacity Reservation IDs	Resource Groups
Default	-	-

Instance type requirements

This Auto Scaling group will adhere to the launch template.

Step 3: Integrate with other services

Edit

Load balancing

Load balancer 1

Name	Type	Target group
MediCore-ASG-1	Application/HTTP	MediCore-TG

VPC Lattice integration options

VPC Lattice target groups

-

Application Recovery Controller (ARC) zonal shift

ARC zonal shift

Disabled

Health checks

Health check type	Health check grace period
EC2, ELB	300 seconds

Step 4: Configure group size and scaling policies

Edit

Group size

Desired capacity	Desired capacity type
2	Units (number of instances)

Scaling

Minimum desired capacity	Maximum desired capacity
2	4

Target tracking policy	Scaling policy name	Execute policy when
Policy type	Target Tracking Policy	As required to maintain Average CPU utilization at 70
Target tracking scaling		
Take the action	Instances need	Scale in
Add or remove capacity units as required	300 seconds to warm up before including in metric	Enabled

Instance maintenance policy

Replacement behavior	Min healthy percentage	Max healthy percentage
No policy	-	-

Additional settings

Instance scale-in protection	Monitoring	Default instance warmup
Disabled	Enabled	Disabled
Placement group	Auto Scaling group deletion protection	
-	None (default)	

Step 5: Add notifications

Edit

Notifications

No notifications

Step 6: Add tags

Edit

Tags (0)

Key	Value	Tag new instances
		No tags

Preview code

Cancel

Previous

Create Auto Scaling group