



# PunkBackup — Desktop App Usage Manual

---

This manual shows the app in **English** — go to "**Settings**" → "**English**" if it isn't already switched. For first-time setup, see the **Installation Manual**; for problems, see the **Troubleshooting Manual**.

## The window has 2 screens

---

- **"Main"**: turn the backup server on/off, see the address your devices should connect to, and each profile's status.
- **"Settings"**: switch the app's language, and create/manage each person or device (profiles).

Switch between them with the two buttons at the top, right under the app name.

The window opens **maximized** by default every time — resize/un-maximize it as usual if you'd rather have it smaller; that's a normal Windows window control, not something PunkBackup remembers between launches.

---

## "Settings" → Language

---

At the very top of Settings there are two buttons: **Español / English**. Tap one and **the whole app switches language instantly** — buttons, titles, messages, everything — no closing or restarting needed. Your choice is remembered the next time you open the app.

In the top-right corner of that same card, and also in the window's title bar, you'll see which version you have installed (e.g. "PunkBackup v1.7.3") — useful if you're comparing against this manual or reporting an issue.

---

## "Settings" → Preferences

---

Right below Language, three cards — same on/off switch style as each profile's Active/Paused switch on the "Main" screen. Every change here applies immediately, no restart needed.

- **Start PunkBackup with Windows**: adds (or removes) PunkBackup from Windows' own startup programs, so it opens automatically when you log in — no need to find the Desktop icon every time. **Off by default**.
- **Start backup when opening the app**: as soon as the app finishes opening, it automatically does the same thing as clicking "**Start backup**" yourself — including the same warnings if no profile is configured yet, or none has a destination folder set. Combine this with the switch above for a PC that starts listening

for your iPhone completely hands-off after a reboot. **Off by default.**

- **Minutes of inactivity before flagging the backup as stopped:** a number field (1–30 minutes) controlling the idle-backup notice described above under "▼ Show activity". Type a new value and click **"Save"** (or press Enter) — the button only lights up while there's an unsaved, valid change, and briefly shows "Saved" once it's applied, so it's always clear whether your edit actually took effect. **5 minutes by default.**

---

## "Main" screen

---

### "Start backup" / "Stop backup" button

This is the server's main on/off switch — it controls whether the PC is **listening** on the network at all.

- **Off** ("Start backup", green): your PC accepts no connections from any iPhone/iPad. This is the default — the app never turns itself on, even if left open.
- **On** ("Stop backup", red): your PC can now receive photos and videos from any **Active** profile.

Right next to it, the **"Status: ..."** text confirms the mode: Stopped, Starting backup... (briefly, right after clicking — usually just a couple seconds, occasionally longer if the port needs a moment to free up, e.g. right after antivirus software closes and reopens the app), or Listening on port 8787. If starting genuinely fails (the port stays unavailable), you'll get an error window explaining why instead of a false "Listening" status.

You don't need to "select" which profile is backing up — as long as the server is on, **any Active profile can upload at any time**, even several at once.

### "Server address (same for every profile):"

Two values you'll only need **once**, when setting up each iPhone/iPad's Shortcut (they don't change per profile):

- **Address:** `http://YOUR-PC-NAME.local:8787` — try this first.
- **Fallback IP:** a numeric backup address, in case the one above doesn't resolve from a particular iPhone.

### "Profiles connected to this backup:"

One card per profile you've created, showing:

- **Name** of the profile.
- **Total in destination:** how many files are in that profile's folder in total (everything backed up so far, across every run), plus the date of the last backup.
- **Last run:** how many files were saved specifically in the Shortcut's most recent run (new vs. already had) — if that run is still going, it's marked "(in progress...)".
- **Folder:** where it's saving its files.
- **USB:** if its folder is on a removable drive, that drive's label and free space.
- An **Active / Paused** switch — see below.

## The Active / Paused switch

This is different from the big button above. That one turns **the whole PC** on/off; this switch blocks or allows **one specific profile**, without touching the others.

- **Active**: that device can upload normally.
- **Paused**: that specific device can't upload anything (the server replies "profile paused"), while everyone else keeps working. Useful, for example, to cut off a guest's device without deleting its history.

Pausing/reactivating **deletes nothing** — it's fully reversible.

## "Last backup (all profiles) / Total files"

A combined summary across every profile — a glance to see whether anything backed up recently, without checking each profile individually.

## "▼ Show activity"

**Visible by default** — collapse it with the same button if you want a cleaner screen. It shows a live, terminal-style (green text) log of each file as it arrives: new, already existed, or conflict. Useful to confirm something is actually happening in real time while you run the Shortcut on your iPhone. It also clearly marks when each run **starts** and **finishes** (with the final summary: new/already had/conflicts/errors), so you can see at a glance where each backup begins and ends in the log history.

Every line is stamped with the **local date and time** it happened (DD-MM-YYYY HH:MM:SS), followed by **which profile/device it's about** (e.g. iPhone de Hesner, iPad, or - for a line that isn't about any one profile, like the server starting/stopping) — so with more than one device backing up, you can tell at a glance which line belongs to which one, not just guess from the message text. A log that spans several days (if you leave the app open) still reads clearly either way — you can tell exactly when each backup ran, not just their order.

If a run stays "in progress" without receiving any new file for a while (e.g. WiFi dropped, or you closed the Shortcut on the phone mid-backup), the log shows a notice like ■ "[profile]": no activity for 5+ minutes — the backup looks like it stopped — once per stretch of inactivity, not repeated while it stays idle. How many minutes of inactivity count as "stopped" is configurable — see "Settings" → Preferences below.

Next to that button is a smaller **"Expand"** button, which opens the same log in a separate, larger, resizable window — handy when a long run generates more text than the small embedded panel comfortably shows.

Every line is also saved to a file on disk (%APPDATA%\PunkBackup\logs\activity.log), so past activity can still be checked after closing the app — not just what's currently visible on screen. It rotates daily and automatically deletes anything older than about 6 months, so it never grows forever.

---

## "Settings" → Profiles

---

Below the language switch is where identities are managed — one per person or device.

### "**+** Add profile"

1. Type a name identifying the device (e.g. `iPhone de María`, `iPad de Diego`) — it doesn't need to be technical, it's just so you recognize it.
2. The app generates a unique **token** for that profile and copies it to your clipboard automatically — you'll paste it into that device's Shortcut (see the iPhone Setup Manual).
3. It then asks you to pick that profile's **destination folder** — any folder, on your internal disk or an external USB drive.

### Per-profile buttons

| Button           | What it does                                                                                                                                                                       |
|------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Choose folder... | Changes where that profile saves its files (e.g. if you switched USB drives). Files already backed up in the previous folder are NOT moved or deleted.                             |
| USB history      | Shows the drives/folders that profile has used before — label, serial number, space — so you can recognize which USB is which even if Windows assigns it a different drive letter. |
| Copy token       | Copies the token to your clipboard again (in case you need to reconfigure the Shortcut).                                                                                           |
| Rename           | Changes only the name you see in the app — doesn't affect the token or folder.                                                                                                     |
| Regenerate token | Generates a new token for that profile. That device's Shortcut stops working until you paste the new token in — only use this if you suspect the token leaked.                     |
| Delete           | Revokes that profile's access (its token stops working).<br><b>Does not delete any already-backed-up file.</b>                                                                     |

### Second copy (optional)

Below the buttons, each profile can have a **second copy** — a copy of everything on its main destination, kept on a different folder/USB. Not required, and off by default; it's for anyone who wants their photos on more than one physical drive.

- "**+** Configure second copy (optional)" — appears when you haven't set one up yet. Tap it, choose a folder (it can't be the same folder as your main destination), and you're done configuring it.

- Once configured, you'll see how many files it has and how much free space is left on it, plus a **"Sync now"** button.
  - Tapping **"Sync now"** copies whatever's missing from your main destination to the second copy — newest photos first — and verifies each one after copying, so a bad USB write gets caught and retried automatically instead of silently leaving a broken copy. This never runs on its own; you decide when to sync.
  - While it's syncing, that same button turns into **"■ Stop"** — use it if you need to unplug the second drive before a sync finishes. Nothing is lost either way: whatever was already copied and verified stays, and the next sync picks up exactly where it left off.
  - **"Remove"** stops syncing to that folder — it does **not** delete any file already copied there.
  - If your main drive is ever lost or damaged, this second copy is a real, independent backup: just point your profile's main destination at that folder (using "Choose folder..." above) and the app recognizes exactly what it already has — nothing needs to be re-uploaded from the phone.
- 

## Typical daily use

---

1. Open the app from the Desktop icon.
2. Click **"Start backup"**.
3. Run the Shortcut on your iPhone (manually, or automatically if you set up the WiFi automation).
4. Watch it upload on the "Main" screen (expand "Show activity" for live detail).
5. When you're done, you can close the app or leave it — it does nothing on its own unless you clicked "Start backup".

## Good practices

---

- Create one profile per person or device — never share a token between two iPhones.
- If you're going to use a different USB for someone, just use "Choose folder..." on their profile — no need to create a new one.
- Check "USB history" before plugging in a drive you don't use often, to confirm it's the right one.