Exam AWS Certified Developer - Associate DVA-C02 All Questions

View all questions & answers for the AWS Certified Developer - Associate DVA-C02 exam

Go to Exam

EXAM AWS CERTIFIED DEVELOPER - ASSOCIATE DVA-C02 TOPIC 1 QUESTIO...

Exam question from Amazon's AWS Certified Developer - Associate DVA-C02
Question #: 230
Topic #: 1
[All AWS Certified Developer - Associate DVA-C02 Questions]

A developer registered an AWS Lambda function as a target for an Application Load Balancer (ALB) using a CLI command. However, the Lambda function is not being invoked when the client sends requests through the ALB.

Why is the Lambda function not being invoked?

A. A Lambda function cannot be registered as a target for an ALB.

B. A Lambda function can be registered with an ALB using AWS Management Console only.

C. The permissions to invoke the Lambda function are missing.

D. Cross-zone is not enabled on the ALB.

Show Suggested Answer

---

by Claire_KMT at *Oct. 28, 2023, 2:14 p.m.*

Disclaimers:
- ExamTopics website is **not** related to, affiliated with, endorsed or authorized by Amazon.
- Trademarks, certification & product names are used for reference only and belong to Amazon.

Comments

SerialiDr Highly Voted 2 years, 2 months ago

Selected Answer: C

To allow an ALB to invoke a Lambda function, you need to grant the ALB permission to invoke the Lambda. This is typically done by adding a resource-based policy to the Lambda function, granting invoke permission to the ALB. If this permission is not set, the ALB will not be able to trigger the Lambda function in response to incoming requests.

upvoted 5 times

preachr Most Recent 1 year, 6 months ago

Selected Answer: C

https://docs.aws.amazon.com/elasticloadbalancing/latest/application/lambda-functions.html

Permissions to invoke the Lambda function
If you create the target group and register the Lambda function using the AWS Management Console, the console adds the required permissions to your Lambda function policy on your behalf. Otherwise, after you create the target group and register the function using the AWS CLI, you must use the add-permission command to grant Elastic Load Balancing permission to invoke your Lambda function. We recommend that you use the aws:SourceAccount and aws:SourceArn condition keys to restrict function invocation to the specified target group.

```
aws lambda add-permission \
--function-name lambda-function-arn-with-alias-name \
--statement-id elb1 \
--principal elasticloadbalancing.amazonaws.com \
....
```

upvoted 1 times

65703c1 1 year, 10 months ago

Selected Answer: C

C is the correct answer.

upvoted 1 times

TanTran04 2 years, 3 months ago

Selected Answer: C

The Lambda function must have the lambda:InvokeFunction permission for the ALB to successfully invoke it.

upvoted 3 times

kaes 2 years, 4 months ago

Selected Answer: C

ANS: C

upvoted 3 times

Claire_KMT 2 years, 5 months ago

C. The permissions to invoke the Lambda function are missing.

upvoted 3 times