ID	Title	Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
C114	Add an Item to Wishlist	Himpreet Kaur	3/6/2025 7:44 PM	The item appears in the wishlist	Go to the website "https://www.flipkart. com/" on your browser such as Chrome/Firefox/Safari/ Edge. User is logged in.	High	Happy Path	Expected User Flows	Happy Path	Navigate to a product page Click on "Add to Wishlist" Go to the wishlist page			Wishlist & Favorites	S8	Functional
C115	Remove an Item from Wishlist	Himpreet Kaur	3/6/2025 7:45 PM	Item is removed from wishlist	1. Go to the website https://www.flipkart.com/" on your browser such as Chrome/Firefox/Safari/Edge. 2. User is logged in. 3. Complete Test Case C114.	High	Happy Path	Expected User Flows	Happy Path	Navigate to the "Wishlist" page Click on "Remove" next to the item Confirm deletion			Wishlist & Favorites	S8	Functional
C116	Move Item from Wishlist to Cart	Himpreet Kaur	3/6/2025 7:45 PM		Go to the website "https://www.flipkart.com/" on your browser such as Chrome/Firefox/Safari/Edge. User is logged in. Complete Test Case C114/ have atleast one item in the wishlist.	High	Happy Path	Expected User Flows	Нарру Path	Navigate to Flipkart & log in. Expected Result: User is successfully logged in.	User is successfully logged in.	Navigate to Flipkart & log in.	Wishlist & Favorites	S8	Functional
					parcitase.					Click on the Profile icon and go to Wishlist. Expected Result: Wishlist page is displayed.	Wishlist page is displayed.	Click on the Profile icon and go to Wishlist.			
										Select an item from the wishlist. Expected Result: Item is highlighted with "Move to Cart" option available.	Item is highlighted with "Move to Cart" option available.	Select an item from the wishlist.			
										Click on "Move to Cart" button. Expected Result: The item should be removed from Wishlist and added to Cart.	The item should be removed from Wishlist and added to Cart.	Click on "Move to Cart" button.			
										Navigate to the Cart page. Expected Result: The item should now be present in the Cart with correct details.	The item should now be present in the Cart with correct details.	Navigate to the Cart page.			
										Return to the Wishlist page and refresh. Expected Result: The moved item should no longer be in the Wishlist.	The moved item should no longer be in the Wishlist.	Return to the Wishlist page and refresh.			
C117	Add Out-of-Stock Item to Wishlist	Himpreet Kaur	3/6/2025 7:45 PM		1. Go to the website https://www.flipkart.com/* on your browser such as Chrome/Firefox/Safari/Edge. 2. User is logged in. 3. Complete Test Case C114/ have atleast one item in the wishlist. 4. The item must be	Medium	Happy Path	Expected User Flows	Happy Path	Navigate to Flipkart & log in. Expected Result: User is successfully logged in.	User is successfully logged in.	Navigate to Flipkart & log in.	Wishlist & Favorites	\$8	Functional
					marked as "Out of Stock" on the product page.					Search for an out-of-stock					
										product. Expected Result: The product page is displayed with an "Out of Stock" label.	The product page is displayed with an "Out of Stock" label.	Search for an out- of-stock product.			

ID	Title	Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
										Click on the "Add to Wishlist" button. Expected Result: The item should be successfully added to the Wishlist.	The item should be successfully added to the Wishlist.	Click on the "Add to Wishlist" button.			
										Navigate to the Wishlist page. Expected Result: The out-of-stock item should appear in the Wishlist.	The out-of-stock item should appear in the Wishlist.	Navigate to the Wishlist page.			
										Refresh the page and check the Wishlist. Expected Result: The item should still be present in the Wishlist.	The item should still be present in the Wishlist.	Refresh the page and check the Wishlist.			
C118	Verify Wishlist Item Details	Himpreet Kaur	3/6/2025 7:45 PM		1. Go to the website "https://www.flipkart.com/" on your browser such as Chrome/Firefox/Safari/Edge. 2. User is logged in. 3. Complete Test Case C114/ have atteast one item in the wishlist.	High	Happy Path	Expected User Flows	Happy Path	Navigate to Flipkart and log in. Expected Result: User is successfully logged in.	User is successfully logged in.	Navigate to Flipkart and log in.	Wishlist & Favorites	\$8	Functional
										Click on the Wishlist section.					
										Expected Result: The Wishlist page is displayed.	The Wishlist page is displayed.	Click on the Wishlist section.			
										Verify that the saved items are displayed correctly. Expected Result: Items should appear with their respective details.	Items should appear with their respective details.	Verify that the saved items are displayed correctly.			
										Check the product name, price, availability, and image. Expected Result: All details should match the actual product listing.	All details should match the actual product listing.	Check the product name, price, availability, and image.			
										Verify that clicking the item name or image redirects to the product page. Expected Result: The user should be taken to the correct product page.	The user should be taken to the correct product page.	Verify that clicking the item name or image redirects to the product page.			
C119	Test Wishlist Page Responsiveness	Himpreet Kaur	3/6/2025 7:49 PM		1. Go to the website "https://www.flipkart.com/" on your browser such as Chrome/Firefox/Safari/Edge. 2. User is logged in. 3. Complete Test Case C114/ have atleast one item in the wishlist.	Medium	Happy Path	Expected User Flows	Happy Path	Open the Flipkart website on a desktop browser (Chrome, Edge, Firefox). Expected Result: Wishlist page should load correctly with all elements visible.	Wishlist page should load correctly with all elements visible.	Open the Flipkart website on a desktop browser (Chrome, Edge, Firefox).	Wishlist & Favorites	S8	Compatibili ty
										Resize the browser window to a tablet screen size (e.g., 768x1024 pixels). Expected Result: The page layout should adjust properly, without overlapping or broken elements.	The page layout should adjust properly, without overlapping or broken elements.	Resize the browser window to a tablet screen size (e.g., 768x1024 pixels).			
										Open the Flipkart website on a mobile browser (Android/IOS, Chrome, Safari). Expected Result: Wishlist page should display in a mobile-friendly layout.	Wishlist page should display in a mobile-friendly layout.	Open the Flipkart website on a mobile browser (Android/iOS, Chrome, Safari).			
										Verify scrolling behavior on all devices. Expected Result: Scrolling should be smooth, and all wishlist items should be accessible.	Scrolling should be smooth, and all wishlist items should be accessible.	Verify scrolling behavior on all devices.			

ID	Title	Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
										Check if wishlist items, product details, and buttons (Move to Cart, Remove) are clearly visible and clickable on all screen sizes. Expected Result: Buttons and text should be properly aligned and functional.	Buttons and text should be properly aligned and functional.	Check if wishlist items, product details, and buttons (Move to Cart, Remove) are clearly visible and clickable on all screen sizes.			
										Rotate the mobile device to landscape mode. Expected Result: The layout should adjust without distortion or overlapping elements.	The layout should adjust without distortion or overlapping elements.	Rotate the mobile device to landscape mode.			
										Test on different screen resolutions (Full HD, 4K, small mobile screens). Expected Result: The Wishlist page should be visually consistent and responsive.	The Wishlist page should be visually consistent and responsive.	Test on different screen resolutions (Full HD, 4K, small mobile screens).			
C120	Verify Wishlist Sync Between Web & Mobile	Himpreet Kaur	3/6/2025 7:49 PM		User must have a registered Flipkart account and be logged in on both web (desktop browser) and Flipkart mobile app. Internet connection should be active on both devices.	Critical	Happy Path	Expected User Flows	Happy Path	Open Flipkart on a desktop browser and log in. Expected Result: User should be logged in successfully.	User should be logged in successfully.	Open Flipkart on a desktop browser and log in.	Wishlist & Favorites	S8	Compatibili ty
										Navigate to a product page and click "Add to Wishlist". Expected Result: Product should be added to Wishlist successfully.	Product should be added to Wishlist successfully.	Navigate to a product page and click "Add to Wishlist".			
										Open the Flipkart mobile app on the same account. Expected Result: The user should be logged in automatically if previously logged in.	The user should be logged in automatically if previously logged in.	Open the Flipkart mobile app on the same account.			
										Navigate to the Wishlist section on the mobile app. Expected Result: The recently added product from the web should be visible in the mobile Wishlist.	The recently added product from the web should be visible in the mobile Wishlist.	Navigate to the Wishlist section on the mobile app.			
										Remove the item from the mobile app Wishlist. Expected Result: Product should be removed successfully from the Wishlist.	Product should be removed successfully from the Wishlist.	Remove the item from the mobile app Wishlist.			
										Refresh the Wishlist page on the desktop website. Expected Result: The item should no longer appear in the Wishlist.	The item should no longer appear in the Wishlist.	Refresh the Wishlist page on the desktop website.			
										Repeat the process by adding an item from the mobile app and verifying on the web. Expected Result: Wishlist should sync properly in both directions.	Wishlist should sync properly in both directions.	Repeat the process by adding an item from the mobile app and verifying on the web.			
					Go to the website "https://www.flipkart. com/" on your browser such as Chrome/Firefox/Safari/ Edge					Open the Flipkart website and		On an the Filed	NATIONAL STATE		
C123	Check Wishlist Search & Filter	Himpreet Kaur	3/6/2025 7:57 PM		Edge. 2. User is logged in. 3. Complete Test Case C114 for multiple items / must have multiple	High	Happy Path	Expected User Flows	Happy Path	log in. Expected Result: User should be logged in successfully.	User should be logged in successfully.	Open the Flipkart website and log in.	Wishlist & Favorites	S8	Functional
					items in the Wishlist.					Navigate to the Wishlist section. Expected Result: The saved items should be displayed.	The saved items should be displayed.	Navigate to the Wishlist section.			

ID	Title	Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
										Click on the Search bar within the Wishlist. Expected Result: A search input field should be available for entering keywords.	A search input field should be available for entering keywords.	Click on the Search bar within the Wishlist.			
										Enter a valid product name (that exists in the Wishlist). Expected Result: The correct product should be filtered and displayed.	The correct product should be filtered and displayed.	Enter a valid product name (that exists in the Wishlist).			
										Enter a random product name (that does not exist in the Wishlist). Expected Result: No results should be shown with a "No items found" message.	No results should be shown with a "No items found" message.	Enter a random product name (that does not exist in the Wishlist).			
										Apply category filter (e.g., Electronics, Fashion). Expected Result: Only items matching the selected category should be displayed.	Only items matching the selected category should be displayed.	Apply category filter (e.g., Electronics, Fashion).			
										Apply price filter (e.g., ₹500 - ₹1000). Expected Result: Only items within the selected price range should be displayed.	Only items within the selected price range should be displayed.	Apply price filter (e.g., ₹500 - ₹1000).			
										Apply discount filter (e.g., 20% Off). Expected Result: Only items matching the selected discount percentage should be displayed.	Only items matching the selected discount percentage should be displayed.	Apply discount filter (e.g., 20% Off).			
										Apply multiple filters together (e.g., Category + Price + Discount). Expected Result: Wishlist items should be filtered correctly according to applied criteria.	Wishlist items should be filtered correctly according to applied criteria.	Apply multiple filters together (e. g., Category + Price + Discount).			
										Remove all filters and reset the Wishlist view. Expected Result: The entire Wishlist should be displayed again.	The entire Wishlist should be displayed again.	Remove all filters and reset the Wishlist view.			
	Attempt to Add				1. Go to the website "https://www.flipkart. com/" on your browser such as Chrome/Firefox/Safari/ Edge.					Open the Flipkart website and log in.	User should be logged in	Open the Flipkart	Wishlist		
C121	Removed Product to Wishlist	Himpreet Kaur	3/6/2025 7:50 PM		User is logged in. Complete Test Case C114 for multiple items / must have multiple items in the Wishlist.	Medium	Sad Path	Negative Scenarios	Sad Path	Expected Result: User should be logged in successfully.	successfully.	website and log in.	& Favorites	S8	Functional
					items in the Wishinst.					Navigate to the Wishlist section. Expected Result: The Wishlist should be displayed.	The Wishlist should be displayed.	Navigate to the Wishlist section.			
										Identify a previously removed item from the Wishlist. Expected Result: Ensure that the product was removed earlier.	Ensure that the product was removed earlier.	Identify a previously removed item from the Wishlist.			
										Search for the same product in the Flipkart catalog. Expected Result: The product page should be accessible.	The product page should be accessible.	Search for the same product in the Flipkart catalog.			
										Click on the "Add to Wishlist" button for the removed item. Expected Result: The product should be successfully added back to the Wishlist.	The product should be successfully added back to the Wishlist.	Click on the "Add to Wishlist" button for the removed item.			
										Navigate to the Wishlist section again. Expected Result: The product should now be visible in the Wishlist.	The product should now be visible in the Wishlist.	Navigate to the Wishlist section again.			

ID	Title	Created By	Created On Ex	pected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
										Attempt to remove and add the same product multiple times. Expected Result: The system should allow repeated addition and removal without errors.	The system should allow repeated addition and removal without errors.	Attempt to remove and add the same product multiple times.			
C122	Try Adding Wishlist Items While Logged Out	Himpreet Kaur	3/6/2025 7:50 PM		Go to the website "https://www.flipkart.com/" on your browser such as Chrome/Firefox/Safari/Edge. User must NOT logged in.	High	Sad Path	Negative Scenarios	Sad Path	Open the Flipkart website or mobile app without logging in. Expected Result: The homepage should load successfully.	The homepage should load successfully.	Open the Flipkart website or mobile app without logging in.	Wishlist & Favorites	S8	Functional
										Search for any product using the search bar. Expected Result: The search results should display available products.	The search results should display available products.	Search for any product using the search bar.			
										Click on a product to open its details page. Expected Result: The product details should load properly.	The product details should load properly.	Click on a product to open its details page.			
										Locate the "Add to Wishlist" button and click on it. Expected Result: The system should prompt the user to log in before adding the item.	The system should prompt the user to log in before adding the item.	Locate the "Add to Wishlist" button and click on it.			
										Attempt to navigate to the Wishlist page manually. Expected Result: The system should redirect the user to the login/signup page or show an appropriate error message.	The system should redirect the user to the login/signup page or show an appropriate error message.	Attempt to navigate to the Wishlist page manually.			
										Complete the login process when prompted and check the Wishlist. Expected Result: If the user logs in, the product should now be in the Wishlist.	If the user logs in, the product should now be in the Wishlist.	Complete the login process when prompted and check the Wishlist.			
										Try refreshing the page before logging in and clicking "Add to Wishlist" again. Expected Result: The system should still prompt for login, ensuring no items are added anonymously.	The system should still prompt for login, ensuring no items are added anonymously.	Try refreshing the page before logging in and clicking "Add to Wishlist" again.			
C124	Remove Wishlist Item Multiple Times Quickly	Himpreet Kaur	3/6/2025 7:57 PM		1. Go to the website "https://www.flipkart.com/" on your browser such as Chrome/Firefox/Safari/Edge. 2. User must be logged in. 3. Complete testcase C114 for multiple items.	Medium	Sad Path	Negative Scenarios	Sad Path	Open the Flipkart website and navigate to the Wishlist. Expected Result: Wishlist should load successfully, displaying saved items.	Wishlist should load successfully, displaying saved items.	Open the Flipkart website and navigate to the Wishlist.	Wishlist & Favorites	S8	Destructive
										Identify an item in the Wishlist and click the "Remove" button. Expected Result: The item should be successfully removed, and the page should update accordingly.	The item should be successfully removed, and the page should update accordingly.	Identify an item in the Wishlist and click the "Remove" button.			
										Immediately click the "Remove" button multiple times quickly (before the page refreshes). Expected Result: The system should prevent multiple deletions of the same item and avoid UI glitches.	The system should prevent multiple deletions of the same item and avoid UI glitches.	Immediately click the "Remove" button multiple times quickly (before the page refreshes).			

ID Title		Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
										Refresh the Wishlist page. Expected Result: The removed item should not reappear in the Wishlist.	The removed item should not reappear in the Wishlist.	Refresh the Wishlist page.			
										Navigate to another page and return to Wishlist. Expected Result: The removed item should not be present.	The removed item should not be present.	Navigate to another page and return to Wishlist.			
										Attempt to undo the removal if an "Undo" option is available. Expected Result: If available, the system should restore the item without errors.	If available, the system should restore the item without errors.	Attempt to undo the removal if an "Undo" option is available.			
										Monitor loading time and responsiveness while removing multiple items quickly. Expected Result: The page should remain responsive and not crash.	The page should remain responsive and not crash.	Monitor loading time and responsiveness while removing multiple items quickly.			
C125 Try Adding Items	J Duplicate	Himpreet Kaur	3/6/2025 7:58 PM		Go to the website "https://www.flipkart. com/" on your browser such as Chrome/Firefox/Safari/ Edge. User must be logged in.	Medium	Sad Path	Negative Scenarios	Sad Path	Open the Flipkart website and navigate to any product page. Expected Result: The product page should load successfully.	The product page should load	Open the Flipkart website and navigate to any product page.	Wishlist & Favorites	S8	Destructive
										Click on the "'Add to Wishlist" button. Expected Result: The product should be successfully added to the Wishlist.	The product should be successfully added to the Wishlist.	Click on the "Add to Wishlist" button.			
										Navigate to the Wishlist page to verify if the product is listed. Expected Result: The Wishlist should display the added product.	The Wishlist should display the added product.	Navigate to the Wishlist page to verify if the product is listed.			
										Return to the same product page and try clicking "Add to Wishlist" again. Expected Result: The system should prevent duplicate entries and show an appropriate message (e.g., "This item is already in your Wishlist").	The system should prevent duplicate entries and show an appropriate message (e.g., This item is already in your Wishlist*).	Return to the same product page and try clicking "Add to Wishlist" again.			
										Navigate back to the Wishlist page and check if the product appears multiple times. Expected Result: The product should only appear once in the Wishlist.	The product should only appear once in the Wishlist.	Navigate back to the Wishlist page and check if the product appears multiple times.			
										Try adding the same product from a different browser/session/device. Expected Result: The system should sync correctly, preventing duplicates.	The system should sync correctly, preventing duplicates.	Try adding the same product from a different browser/session/device.			
										Attempt to add a duplicate Wishlist item by changing product attributes (e.g., color, size) if applicable. Expected Result: If variations are treated as separate items, they should be added individually. Otherwise, duplication should be prevented.	If variations are treated as separate items, they should be added individually. Otherwise, duplication should be prevented.	Attempt to add a duplicate Wishlist item by changing product attributes (e.g., color, size) if applicable.			

ID	Title	Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
C126	Delete All Items & Refresh Wishlist	Himpreet Kaur	3/6/2025 7:58 PM		1. Go to the website 'https://www.lipkart.com/' on your browser such as Chrome/Firefox/Safari/Edge. 2. User must be logged in. 3. Complete test case C114 or have at least two or more products must be added to the	High	Sad Path	Negative Scenarios	Sad Path	Open the Flipkart website and navigate to the Wishlist page. Expected Result: Wishlist page should display all previously added items.	Wishlist page should display all previously added items.	Open the Flipkart website and navigate to the Wishlist page.	Wishlist & Favorites	S8	Regression
					Wishlist.					Verify the count of items in the Wishlist before deletion. Expected Result: The Wishlist should display the correct item count.	The Wishlist should display the correct item count.	Verify the count of items in the Wishlist before deletion.			
										Click the delete (remove) button for each item in the Wishlist. Expected Result: The selected item should be removed from the Wishlist.	The selected item should be removed from the Wishlist.	Click the delete (remove) button for each item in the Wishlist.			
										If available, use the "Remove All" option (if provided by Flipkart). Expected Result: All items should be deleted from the Wishlist in one action.	All items should be deleted from the Wishlist in one action.	If available, use the "Remove All" option (if provided by Flipkart).			
										Confirm that the Wishlist is empty before refreshing the page. Expected Result: The Wishlist should display a message like ""Your Wishlist is Empty".	The Wishlist should display a message like "Your Wishlist is Empty".	Confirm that the Wishlist is empty before refreshing the page.			
										Refresh the Wishlist page using browser refresh. Expected Result: The Wishlist should remain empty after refresh.	The Wishlist should remain empty after refresh.	Refresh the Wishlist page using browser refresh.			
										Log out and log back into the account, then navigate to the Wishlist page again. Expected Result: The Wishlist should still be empty.	The Wishlist should still be empty.	Log out and log back into the account, then navigate to the Wishlist page again.			
					Go to the website 'https://www.flipkart. com/' on your browser such as Chrome/Firefox/Safari/ Edge. User must be logged in.					Open the Flipkart website or mobile app and navigate to		Open the Flipkart website or mobile	Wishlist		
C127	Attempt SQL Injection on Wishlist	Himpreet Kaur	3/6/2025 8:00 PM		3. Complete test case C114 or have at least two or more products must be added to the Wishlist. 4. Developer tools or a testing proxy (e.g., Burp.)	Critical	Sad Path	Negative Scenarios	Sad Path	the Wishlist page. Expected Result: The Wishlist page should load normally.	The Wishlist page should load normally.	app and navigate to the Wishlist page.		\$8	Security
					Suite, Postman) can be used to manipulate requests.					Try adding an item to the					
										I'vi adoing an item to the Wishlist using an SQL injection payload in the product ID field. Example: 105 OR 1=1 — Expected Result: The system should reject the request and not add an unauthorized Item to the Wishlist.	The system should reject the request and not add an unauthorized item to the Wishlist.	Try adding an item to the Wishlist using an SQL injection payload in the product ID field. Example: 105 OR 1=1 -			

ID Title	Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
									Modify the Wishlist search or filter field using SQL injection payloads like: 'DROP TABLE wishlist, — 'UNION SELECT NULL, NULL, NULL — Expected Result: The system should sanitize inputs and prevent malicious execution. No unintended data should be exposed.	The system should sanitize inputs and prevent malicious execution. No unintended data should be exposed.	Modify the Wishlist search or filter field using SQL injection payloads like: '; DROP TABLE wishlist; - ' UNION SELECT NULL, NULL, NULL -			
									Attempt SQL injection in the Remove from Wishlist request by manipulating the request payload. Example: DELETE FROM wishlist WHERE user_id='105' OR '1'='1' Expected Result: The system should validate user permissions and prevent mass deletion or unauthorized actions.	The system should validate user permissions and prevent mass deletion or unauthorized actions.	Attempt SQL injection in the Remove from Wishlist request by manipulating the request payload. Example: DELETE FROM wishlist WHERE user_id='105' OR '1'='1'			
									Capture a wishlist API request and modify its parameters with SQL injection syntax, then resend the request. Example: GET /wishlist?id='OR 1=1 - Expected Result: The request should fail securely, returning an error or handling it safely without affecting the database.	The request should fail securely, returning an error or handling it safely without affecting the database.	Capture a wishlist API request and modify its parameters with SQL injection syntax, then resend the request. Example: GET /wishlist?id=' OR 1=1 —			
									Attempt SQL injection using input fields (if applicable) on the Wishlist page. Example: Entering 'OR 1's-1' in search or comments fields. Expected Result: The input should be sanitized, and no SQL queries should be executed.	The input should be sanitized, and no SQL queries should be executed.	Attempt SQL injection using input fields (if applicable) on the Wishlist page. Example: Entering 'OR'1'='1 in search or comments fields.			
									Check the response messages for any database errors or unhandled exceptions (e.g., SQL syntax errors). Expected Result: The system should handle errors gracefully, without exposing SQL database details.	The system should handle errors gracefully, without exposing SQL database details.	Check the response messages for any database errors or unhandled exceptions (e.g., SQL syntax errors).			
C128 Add 1000+ Items to Wishlist	Himpreet Kaur	3/6/2025 8:01 PM		1. Go to the website https://www.flipkart. com/* on your browser such as Chrome/Firefox/Safari/ Edge. 2. User must be logged in.	High	Edge Case	Uncommon or Extreme Scenarios	Edge Case	Log in to the Flipkart website. Expected Result: User is successfully logged in.	User is successfully logged in.	Log in to the Flipkart website.	Wishlist & Favorites	\$8	Performan ce
									Navigate to the Wishlist page. Expected Result: Wishlist page loads correctly.	Wishlist page loads correctly.	Navigate to the Wishlist page.			
									Start adding items to the Wishlist one by one using the 'Add to Wishlist' button on multiple products. (Or Follow testcase C114) Expected Result: Items should be added successfully.	Items should be added successfully.	Start adding items to the Wishlist one by one using the "Add to Wishlist" button on multiple products. (Or Follow testcase C114)			
									Use bulk addition methods (if available) to add multiple items at once. Expected Result: Wishlist should update accordingly without errors.	Wishlist should update accordingly without errors.	Use bulk addition methods (if available) to add multiple items at once.			

ID	Title	Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
										Continue adding items until the Wishlist contains 1000+ products. Expected Result: The system should handle the load without crashes.	The system should handle the load without crashes.	Continue adding items until the Wishlist contains 1000+ products.			
										Try adding one more item beyond 10004 products. Expected Result: If a Wishlist limit exists, the system should display an error message like "Wishlist limit reached."	If a Wishlist limit exists, the system should display an error message like "Wishlist limit reached."	Try adding one more item beyond 1000+ products.			
										Refresh the Wishlist page and verify that all 1000+ items are still visible. Expected Result: No data loss should occur.	No data loss should occur.	Refresh the Wishlist page and verify that all 1000+ items are still visible.			
										Attempt to navigate, search, or filter through the Wishlist after adding 1000+ items. Expected Result: The page should remain responsive with acceptable load times.	The page should remain responsive with acceptable load times.	Attempt to navigate, search, or filter through the Wishlist after adding 1000+ items.			
										Try removing an item from the Wishlist after reaching the limit. Expected Result: The item should be removed successfully.	The item should be removed successfully.	Try removing an item from the Wishlist after reaching the limit.			
										Log out and log back in, then check if all Wishlist items persist. Expected Result: Data should be retained across sessions.	Data should be retained across sessions.	Log out and log back in, then check if all Wishlist items persist.			
					Go to the website "https://www.flipkart. com/" on your browser such as Chrome/Firefox/Safari/ Edge. Go to the website "https://www.flipkart. Edge. Go to the website "https://www.flipkart. Edge. Go to the website "https://www.flipkart. Go no. Go no.					Log in to the Flipkart website.					
C129	Delete All Items & Immediately Add Another	Himpreet Kaur	3/6/2025 8:01 PM		User must be logged in.	Medium	Edge Case	Uncommon or Extreme Scenarios	Edge Case	Expected Result: User is successfully logged in.	User is successfully logged in.	Log in to the Flipkart website.	Wishlist & Favorites	S8	Usability
					Complete testcase C114 / Wishlist must contain at least 5 items before starting the test.										
										Navigate to the Wishlist page. Expected Result: Wishlist page loads correctly.	Wishlist page loads correctly.	Navigate to the Wishlist page.			
										Ensure there are multiple items in the Wishlist (at least 5). Expected Result: Wishlist displays all items correctly.	Wishlist displays all items correctly.	Ensure there are multiple items in the Wishlist (at least 5).			
										Click "Delete All" or manually remove each item. Expected Result: All Wishlist items should be removed successfully.	All Wishlist items should be removed successfully.	Click "Delete All" or manually remove each item.			
										Without refreshing the page, immediately attempt to add a new item to the Wishlist. Expected Result: The item should be added successfully without errors.	The item should be added successfully without errors.	Without refreshing the page, immediately attempt to add a new item to the Wishlist.			
										Refresh the Wishlist page and verify the new item is persistently stored. Expected Result: The newly added item should still be in the Wishlist.	The newly added item should still be in the Wishlist.	Refresh the Wishlist page and verify the new item is persistently stored.			
										Logout and log back in, then check if the Wishlist reflects the correct state. Expected Result: Deleted items should remain deleted, and the new item should be present.	Deleted items should remain deleted, and the new item should be present.	Logout and log back in, then check if the Wishlist reflects the correct state.			

ID	Title	Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
C130	Add Items with Unstable Internet	Himpreet Kaur	3/6/2025 8:01 PM		1. Go to the website "https://www.flipkart.com/" on your browser such as Chrome/Firefox/Safari/Edge. 2. User must be logged in. 3. User must have access to a slow or unstable internet connection (e.g., simulate via network throttling tools, Wi-Fi toggling, or mobile data switching). before starting the test.	High	Edge Case	Uncommon or Extreme Scenarios	Edge Case	Log in to the Flipkert website Expected Result: User successfully logs in.	User successfully logs in.	Log in to the Flipkart website	Wishlist & Favorites	S8	Performan ce
										Navigate to the Wishlist page. Expected Result: Wishlist page loads correctly.	Wishlist page loads correctly.	Navigate to the Wishlist page.			
										Enable unstable network conditions (e.g., switch between Wi-Fi and mobile data, enable network throttling). Expected Result: Internet connectivity becomes unstable.	Internet connectivity becomes unstable.	Enable unstable network conditions (e.g., switch between Wi-Fi and mobile data, enable network throttling).			
										Try adding multiple items to the Wishlist during unstable connection. Expected Result: Items should either get added successfully or show an appropriate error message.	Items should either get added successfully or show an appropriate error message.	Try adding multiple items to the Wishlist during unstable connection.			
										Refresh the page and verify if the added items are visible in the Wishlist. Expected Result: If items were added successfully, they should persist.	If items were added successfully, they should persist.	Refresh the page and verify if the added items are visible in the Wishlist.			
										Log out and log back in, then check the Wishlist. Expected Result: Only successfully added items should be present.	Only successfully added items should be present.	Log out and log back in, then check the Wishlist.			
										Check for any unexpected errors, delays, or app crashes. Expected Result: System should handle instability gracefully without crashes or data loss.	System should handle instability gracefully without crashes or data loss.	Check for any unexpected errors, delays, or app crashes.			
C131	Modify Wishlist on Two Devices	Himpreet Kaur	3/6/2025 8:01 PM		User must be logged into the same Flipkart account on two different devices (e.g., a desktop browser and a mobile browser). Complete testcase C114 or Wishilst must contain at least one item before testing begins.	High	Edge Case	Uncommon or Extreme Scenarios	Edge Case	Log in to the Flipkart website on Device A (e.g., laptop/desktop). Expected Result: User is logged in and Wishlist is accessible.	User is logged in and Wishlist is accessible.	Log in to the Flipkart website on Device A (e.g., laptop/desktop).	Wishlist & Favorites	S8	Usability
										Log in to the Flipkart mobile browser on Device B (e.g., smartphone/tablet). Expected Result: User is logged in, and the Wishlist syncs automatically.	User is logged in, and the Wishlist syncs automatically.	Log in to the Flipkart mobile browser on Device B (e.g., smartphone/table t).			
										Add a new item to the Wishlist from Device A. Expected Result: Item should immediately reflect on Device B. Remove an existing item	Item should immediately reflect on Device B.	Add a new item to the Wishlist from Device A.			
										Remove an existing item from the Wishlist on Device B. Expected Result: Item should be removed from the Wishlist on Device A upon refresh.	Item should be removed from the Wishlist on Device A upon refresh.	Remove an existing item from the Wishlist on Device B.			

ID	Title	Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
										Edit the quantity or variation of a Wishlist item on Device A (if applicable). Expected Result: Changes should reflect on Device B after synchronization.	Changes should reflect on Device B after synchronization.	Edit the quantity or variation of a Wishlist item on Device A (if applicable).			
										Add multiple items from both devices simultaneously. Expected Result: Wishlist should merge updates correctly, without duplication or loss.	Wishlist should merge updates correctly, without duplication or loss.	Add multiple items from both devices simultaneously.			
										Refresh the Wishlist page on both devices. Expected Result: Changes made on one device should be visible on the other without delay.	Changes made on one device should be visible on the other without delay.	Refresh the Wishlist page on both devices.			
										Log out and log back into both devices, then check the Wishlist. Expected Result: Wishlist should persist with all updates intact.	Wishlist should persist with all updates intact.	Log out and log back into both devices, then check the Wishlist.			
					The user must be logged into a Flipkart account with at least 50 items in the Wishlist. A stable internet connection is required. Test should be					Navigate to the Flipkart Wishlist page on a desktop					
C132	Measure Wishlist Load Time (50+ Items)	Himpreet Kaur	3/6/2025 8:01 PM		conducted on multiple devices (desktop & mobile app) and different browsers (Chrome, Edge, Firefox, Safari). 4. Use a performance testing tool (e.g.,	High	Edge Case	Uncommon or Extreme Scenarios	Edge Case	browser. Expected Result: The Wishist page should start loading without noticeable delay.	The Wishlist page should start loading without noticeable delay.	Navigate to the Flipkart Wishlist page on a desktop browser.	Wishlist & Favorites	S8	Performan ce
					Lighthouse, WebPageTest, or Selenium with timers) to measure load times accurately.										
										Measure the total page load time from request initiation to full content rendering. Expected Result: Page should fully load within 2-5 seconds.	Page should fully load within 2-5 seconds.	Measure the total page load time from request initiation to full content rendering.			
										Scroll through all 50+ items in the Wishlist without interaction delays. Expected Result: Scrolling should be smooth, with no lag or stuttering.	Scrolling should be smooth, with no lag or stuttering.	Scroll through all 50+ items in the Wishlist without interaction delays.			
										Click on a Wishlist item to view its details. Expected Result: The item details page should load within 1-3 seconds.	The item details page should load within 1-3 seconds.	Click on a Wishlist item to view its details.			
										Repeat steps 1-4 on a mobile browser (chrome/Safari). Expected Result: Performance should be similar or slightly faster due to optimized mobile rendering.	Performance should be similar or slightly faster due to optimized mobile rendering.	Repeat steps 1-4 on a mobile browser (Chrome/Safari).			
										Open the Flipkart mobile app, navigate to the Wishlist, and measure load time. Expected Result: App should load the Wishlist within 2-3 seconds.	App should load the Wishlist within 2-3 seconds.	Open the Flipkart mobile app, navigate to the Wishlist, and measure load time.			
										Refresh the Wishlist page to check the reloading performance. Expected Result: Page should reload within an acceptable range (2-4 seconds).	Page should reload within an acceptable range (2-4 seconds).	Refresh the Wishlist page to check the reloading performance.			

ID	Title	Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
										Capture performance metrics using browser developer tools (F12 > Performance tab). Expected Result: Ensure no high CPU/memory spikes or excessive API calls.	Ensure no high CPU/memory spikes or excessive API calls.	Capture performance metrics using browser developer tools (F12 > Performance tab).			
										Compare load times when 50 items vs. 100+ items are in the Wishlist. Expected Result: Any degradation should be minimal (under 1-2 seconds additional load time).	Any degradation should be minimal (under 1-2 seconds additional load time).	Compare load times when 50 items vs. 100+ items are in the Wishlist.			
C133	Stress Test - Add 500+ Items Rapidly	Himpreet Kaur	3/6/2025 8:02 PM		1. The user must be logged into a Flipkart account with a clean or existing Wishlist. 2. A stable internet connection (preferably high-speed broadband). 3. Use a script or automation tool (e.g., Selenium, JMeter, or Locust) to rapidly add items. 4. Browser cache should be cleared before execution to ensure accurate performance results. 5. Test to be conducted on desktop, mobilie web, and mobile app.	Critical	Edge Case	Uncommon or Extreme Scenarios	Edge Case	Open the Flipkart homepage and log in. Expected Result: The user should be logged in successfully.	The user should be logged in successfully.	Open the Flipkart homepage and log in.	Wishlist & Favorites	S8	Performan ce
										Navigate to a product listing page and start adding items to the Wishlist rapidly using a script or manual clicks. Expected Result: Each item should be successfully added.	Each item should be successfully added.	Navigate to a product listing page and start adding items to the Wishlist rapidly using a script or manual clicks.			
										Continuously add 500+ products to the Wishlist within a short time (5-10 minutes). Expected Result: Wishlist count should increase accordingly.	Wishlist count should increase accordingly.	Continuously add 500+ products to the Wishlist within a short time (5-10 minutes).			
										Observe system behavior - check for slowdowns, freezing, or crashes. Expected Result: The system should remain responsive.	The system should remain responsive.	Observe system behavior - check for slowdowns, freezing, or crashes.			
										Refresh the Wishlist page after adding all items. Expected Result: The Wishlist should display all added items correctly.	The Wishlist should display all added items correctly.	Refresh the Wishlist page after adding all items.			
										Scroll through all 500+ items and check if all are correctly listed. Expected Result: No missing or duplicate items should appear.	No missing or duplicate items should appear.	Scroll through all 500+ items and check if all are correctly listed.			
										Restart the browser, log out and log back in, then check the Wishlist. Expected Result: All items should persist after session restart.	All items should persist after session restart.	Restart the browser, log out and log back in, then check the Wishlist.			
										Perform a load test by trying to remove multiple items quickly. Expected Result: No performance degradation or failure should occur.	No performance degradation or failure should occur.	Perform a load test by trying to remove multiple items quickly.			

ID 1	Γitle	Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
										Monitor server response time using browser developer tools or API logs. Expected Result: API requests should not fail or slow down significantly.	API requests should not fail or slow down significantly.	Monitor server response time using browser developer tools or API logs.			
										Check database limits (if applicable) by exceeding 1000+ items. Expected Result: - Flipkart should handle this case smoothly or display a reasonable error message Wishilat should function normally without crashes or missing items Performance logs should be recorded for analysis Flipkart's server/API should not throttle or reject requests unnecessarily.	- Flipkart should handle this case smoothly or display a reasonable error message. - Wishlist should function normally without crashes or missing items. - Performance logs should be recorded for analysis. - Flipkart's server/API should not throttle or reject requests unnecessarily.	Check database limits (if applicable) by exceeding 1000+ items.			
C134 L	Jse Wishlist in ncognito Mode	Himpreet Kaur	3/6/2025 8:02 PM		The user must open Flipkart in an incognito/private browser window. Browser cache and cookies should be disabled (since incognito mode does not store them). Internet connection must be stable. Test to be conducted on desktop and mobile browsers (Chrome, Firefox, Safari, Edge).	Medium	Edge Case	Uncommon or Extreme Scenarios	Edge Case	Open a new Incognito/Private browsing window. Expected Result: The browser should start a private session with no stored cookies.	The browser should start a private session with no stored cookies.	Open a new Incognito/Private browsing window.	Wishlist & Favorites	S8	Security
										Navigate to Flipkart's homepage (https://www. flipkart.com). Expected Result: The site should load normally.	The site should load normally.	Navigate to Flipkart's homepage (https: //www.flipkart. com).			
										Attempt to log in using valid credentials. Expected Result: User should be successfully logged in.	User should be successfully logged in.	Attempt to log in using valid credentials.			
										Go to any product page and add an item to Wishlist. Expected Result: Item should be successfully added to Wishlist.	Item should be successfully added to Wishlist.	Go to any product page and add an item to Wishlist.			
										Open a new incognito tab, log in again, and check the Wishlist. Expected Result: The previously added item should still be visible.	The previously added item should still be visible.	Open a new incognito tab, log in again, and check the Wishlist.			
										Close the incognito window and reopen another one. Log in and check the Wishlist. Expected Result: Wishlist should persist as expected.	Wishlist should persist as expected.	Close the incognito window and reopen another one. Log in and check the Wishlist.			
										Log out of Flipkart in incognito mode and check Wishlist. Expected Result: Wishlist should not be accessible without login.	Wishlist should not be accessible without login.	Log out of Flipkart in incognito mode and check Wishlist.			
										Attempt to add an item to Wishlist without logging in. Expected Result: Flipkart should prompt for login.	Flipkart should prompt for login.	Attempt to add an item to Wishlist without logging in.			
										Try using Wishlist on multiple incognito sessions simultaneously. Expected Result: Wishlist data should sync correctly without conflicts.	Wishlist data should sync correctly without conflicts.	Try using Wishlist on multiple incognito sessions simultaneously.			

ID	Title	Created By	Created On	Expected Result	Preconditions	Priority	Section	Section Description	Section Hierarchy	Steps	Steps (Expected Result)	Steps (Step)	Suite	Suite ID	Туре
										Check for browser session leaks by switching between normal and incognito modes. Expected Result: Wishlist should function the same way in both modes.	Wishlist should function the same way in both modes.	Check for browser session leaks by switching between normal and incognito modes.			
					The user must have at least two Flipkart accounts.										
					A stable internet connection is required.					Open Flipkart website (https:					
C135	Switch Accounts Without Logging Out	Himpreet Kaur	3/6/2025 8:02 PM		 Testing should be performed on both desktop and mobile (browser & Flipkart app). 	High	Edge Case	Uncommon or Extreme Scenarios	Edge Case	//www.flipkart.com). Expected Result: The homepage should load successfully.	The homepage should load successfully.	Open Flipkart website (https: //www.flipkart. com).	Wishlist & Favorites	S8	Security
					Browser cache & cookies should not be cleared between sessions.										
										Log in with Account A. Expected Result: The user should be logged in without issues.	The user should be logged in without issues.	Log in with Account A.			
										Navigate to the Wishlist section and note the items. Expected Result: The Wishlist should display items saved in Account A.	The Wishlist should display items saved in Account A.	Navigate to the Wishlist section and note the items.			
										Without logging out, open a new tab or incognito mode and log in with Account B. Expected Result: The user should be logged into Account B without affecting Account A's session.	The user should be logged into Account B without affecting Account A's session.	Without logging out, open a new tab or incognito mode and log in with Account B.			
										Check the Wishlist section for Account B. Expected Result: The Wishlist should show items for Account B, not Account A.	The Wishlist should show items for Account B, not Account A.	Check the Wishlist section for Account B.			
										Switch back to the Account A tab and refresh the page. Expected Result: Account A's session should remain active and Wishlist should remain unchanged.	Account A's session should remain active and Wishlist should remain unchanged.	Switch back to the Account A tab and refresh the page.			
										Attempt to add an item to Wishilst in Account A while Account B is active in another tab. Expected Result: The item should be successfully added without session conflict.	The item should be successfully added without session conflict.	Attempt to add an item to Wishlist in Account A while Account B is active in another tab.			
										Switch to Account B's tab, refresh, and add a different item to Wishlist. Expected Result: The item should be added to Account B's Wishlist only.	The item should be added to Account B's Wishlist only.	Switch to Account B's tab, refresh, and add a different item to Wishlist.			
										Close the browser completely and reopen Flipkart. Log in with Account A. Expected Result: Account A's Wishlist should be intact.	Account A's Wishlist should be intact.	Close the browser completely and reopen Flipkart. Log in with Account A.			
										Log out from Account A, then log in with Account B. Expected Result: The Wishlist should show items specific to Account B only.	The Wishlist should show items specific to Account B only.	Log out from Account A, then log in with Account B.			