



# S.P.M College, Udantpuri

Bachelor Of Computer Application (BCA)

Part -1 (Paper-1)

– Hira Kumar

## DOS (Disk Operating System)

### External Command

- These commands are not present in the computer's memory but these exists as separate files on the disk. Whenever you type an external command it is first loaded in the RAM and then execute.
- e.g. – Tree, Edit, Attrib, Chkdsk, Comp, Find, Help, Debug, Deltree, Exit, Shutdown

#### 1. MORE

- Using TYPE command we can see the content of any file. But if length of file is greater than 25 lines then remaining lines will scroll up.
- To overcome through this problem we uses MORE command. Using this command we can pause the display after each 25 lines.
- Syntax:- C:\> More <file name>

#### 2. Tree

- This command is used to Graphically display the path of each directory and sub-directory On the drive.
- Syntax – c:\> Tree


```
Administrator: C:\Windows\system32\cmd.exe
E:\>tree
Folder PATH listing
Volume serial number is C640-4BB9
E:
|
|_ gdc
|   |
|   |_ bba
|   |_ bca
```

### 3. DELTREE

- This command is used to delete a directory completely with all its contents.
- Syntax **C:\>DELTREE <Directory name>**
- Note Deltree command only support DOS 5.0 Version, Windows 95, 98, ... Not support Windows 7, 8, 8.1, 10, 11. If you want delete tree directory use internal command RD(Remove) command.

### 4. EDIT

- This command allows the user to view, create and/or modify their computer files.
- Syntax – **c:\> Edit <file name>**



### 5. ATTRIB

- This command allows the user to change the properties or attributes of a specified file.
- For set or remove (Hide / Unhide) the files (.txt, .jpg, .mp4, ...) or directory attributes.
  - ✓ Syntax - **Attrib +h <file/directory> {for hide}**  
**Attrib -h <file/directory> {for unhide}**
- For Read-Only the files attributes.
  - ✓ Syntax – **Attrib +R <file name> {for only read}**  
**Attrib -R <file name> {for remove only read}**

## 6. CHKDSK Command

- This command check the disk status and shows the status report including total disk space, free disk space error and so on.
- Syntax -c:\>CHKDSK [drive name]
- Example c:\> CHKDSK E:
- C:\> chkdsk e: /f (error check & fix)
- C:\> chkdsk e: /r (recover bad sector)

## 7. XCOPY

- This command is used to copy one or more directories including files and sub-directories from one location to another.
- Syntax: C:\> XCOPY <source location> <target location>

C:\> Administrator: C:\Windows\system32\cmd.exe

```
E:\gdc>xcopy e:\gdc\bca e:\gdc\bba
E:\gdc\bca\hira.txt
1 File(s) copied

E:\gdc>xcopy /s/e/t/p e:\gdc\bca e:\gdc\bba
E:\gdc\bca\hira.txt (Y/N)? y
Overwrite E:\gdc\bba\hira.txt (Yes/No/All)? y
E:\gdc\bca\part-1\part1.txt (Y/N)? y

E:\gdc>xcopy /s e:\gdc\bca e:\gdc\bsc
E:\gdc\bca\hira.txt
E:\gdc\bca\part-1\part1.txt
2 File(s) copied

E:\gdc>
```

- ✓ Switch 1. /s – copy only files/Directory with files, not blank directory copy.

Syntax – xcopy /s <source location> <target location>

- ✓ 2. /e – copy all files and directory (empty folder copy)[separate all folder]

Syntax :-c:\> xcopy /e <source location> <target location>

Example :- c:\> xcopy /e e:\spm c:\spm

- ✓ 3. /p -copy all files in available current directory

## 8. LABEL

- This command is used to display and set the volume table of a disk i.e. name for the disk drive.
- Syntax: D:\> LABEL

```
E:\gdc>label
Volume in drive E: has no label
Volume Serial Number is C640-4BB9
Volume label (32 characters, ENTER for none)?

E:\gdc>
```

## 9. Format

- Format is an external command of MS-Dos.
- It is used to prepare a disk for use by erasing all data from the disk.
- Syntax: Format [drive name]
- Example = c:\> Format E:

## 10. Shutdown

- Shutdown is used to turn off or restart the computer.
- /s → shutdown
- /r → restart
- /t n → n is time in second
- Syntax :- c:\> shutdown [switch][time in sec]
- Example :- c:\> shutdown /s /t 5

## ❖ System File

- A **System File** is a file that contains important information required by the **operating system** to start, run, and control the computer. These files are essential for proper functioning of the system. If system files are deleted or damaged, the computer may not work correctly.
- Extension of system file is .sys
- Example – io.sys, msdos.sys,....

### Features:

- Used by the Operating System
- Usually hidden from users
- Automatically loaded at system startup

## ❖ Batch File

- A **Batch File** is a text file that contains a **series of DOS commands**. All commands are executed **automatically one by one** when the batch

file is run.

Batch files are used to save time and automate tasks.

- Extension of Batch file is .bat
- Example – cls,dir,pause,.....

=====HIRA KUMAR=====

1. C:\> help ( to view all internal & external command with uses)
2. C:\>help prompt (normal characters and special codes)

```
C:\Users\hira>help prompt
Changes the cmd.exe command prompt.

PROMPT [text]

    text    Specifies a new command prompt.

Prompt can be made up of normal characters and the following special codes:

$A  & (Ampersand)
$B  | (pipe)
$C  ( (Left parenthesis)
$D  Current date
$E  Escape code (ASCII code 27)
$F  ) (Right parenthesis)
$G  > (greater-than sign)
$H  Backspace (erases previous character)
$L  < (less-than sign)
$N  Current drive
$P  Current drive and path
$Q  = (equal sign)
$S  (space)
$T  Current time
$V  Windows version number
$_  Carriage return and linefeed
$$  $ (dollar sign)

If Command Extensions are enabled the PROMPT command supports
the following additional formatting characters:

$+  zero or more plus sign (+) characters depending upon the
    depth of the PUSHd directory stack, one character for each
    level pushed.

$M  Displays the remote name associated with the current drive
    letter or the empty string if current drive is not a network
    drive.

C:\Users\hira>prompt *hira*$q

*hira*=
```

3. C:\> arrow key up/down to view history of command use by the users OR Press F7

HIRA KUMAR

4. C:\> color a ==> c:\> dir/s

## ❖ **Curl command**

- It is External command of Modern Windows/linux not for Old DOS.
- Curl stands for client URL.
- It is used to transfer data to or from a server using various protocols like HTTP, HTTPS, FTP etc.
- Curl can download files, fetch web pages, or send data.
- Show all curl options → c:\> curl -help

Example: -

- ✓ C:\>curl <https://ppup.ac.in> (fetch and display webpage content)
- ✓ C:\> curl -v <https://ppup.ac.in> (Show detailed request/response info)

## **Funny curl command**

- ✓ C:\> curl ascii.live/forrest
- ✓ C:\> curl ascii.live/rick
- ✓ C:\> color a & curl parrot.live
- ✓ C:\>curl ascii.live/batman
- ✓ C:\>curl ascii.live/donut

5. C:\>ping google.com (this command check for send & received ip packets)
6. C:\>ipconfig (for see system ip address any many), for help -  
C:\>ipconfig /?

```
C:\>ipconfig

Windows IP Configuration

Ethernet adapter Ethernet:

    Media State . . . . . : Media disconnected
    Connection-specific DNS Suffix  . :

Wireless LAN adapter Local Area Connection* 1:

    Media State . . . . . : Media disconnected
    Connection-specific DNS Suffix  . :

Wireless LAN adapter Local Area Connection* 10:

    Media State . . . . . : Media disconnected
    Connection-specific DNS Suffix  . :

Wireless LAN adapter Wi-Fi:

    Connection-specific DNS Suffix  . :
    IPv6 Address. . . . . : 2409:40e4:49:89b4:6d99:8742:14f8:d3b2
    Temporary IPv6 Address. . . . . : 2409:40e4:49:89b4:ad0f:e2c:bfd5:e5e1
    Link-local IPv6 Address . . . . . : fe80::6d99:8742:14f8:d3b2%4
    IPv4 Address. . . . . : 192.168.46.27
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : fe80::9cb6:76ff:fe09:8d68%4
                                192.168.46.124

Ethernet adapter Bluetooth Network Connection:

    Media State . . . . . : Media disconnected
    Connection-specific DNS Suffix  . :

C:\>
```

=====HIRA KUMAR=====