Facecraft Bukkit Server Management

User Manual

This manual will show you how you can set up your Minecraft server on the Facecraft Network and manage it all from the app.

Bukkit Plugin

The first step is to install the Facecraft Bukkit Plugin on your Minecraft server. Obtain the latest version of the Bukkit Plugin and follow these next steps:

1. Add the .jar file to your *plugins* folder
2. Restart your Minecraft Server
3. Ensure that the Facecraft plugin is loaded. This can be done by looking in the server terminal and seeing it Facecraft is enabled. If you see a connection error, this means Facecraft Central Servers are currently down, so just try again later.

Connecting to Facecraft Central Server

To use the Facecraft app services, you first need to register and connect to the Facecraft Central Server. If you have already registered this server before, you can skip to the connection step.

1. Register your Minecraft server by providing your server's address (IP or domain), a password to use for later authentication, and the name of your server (can be multiple words).

```
> facecraft register <address> <password> <Name...>
```

If you have issues registering, please read the error message and try something else

2. Once you have successfully registered, connect your server.

```
> facecraft connect <address> <password>
```

Use the same info that you used to register. Please note that this information is not stored in configuration files, so you need to run it every time you reboot your server.

You should now be all set up on the Facecraft Network. Next you will learn how to manage owners so you can start managing the server from the app.

Managing Server Owners

Facecraft supports adding and removing server owners directly from the Minecraft server terminal window. This means that you always have ultimate control over the moderation of your server.

Here is how you add owners:

```
> facecraft addowner <facecraft-username>
```

And to remove them:

```
> facecraft removeowner <facecraft-username>
```

Make sure to use their Facecraft usernames. Please note that these may be different than their in-game Minecraft usernames.

Managing Your Server On-the-Go

One of the most useful features of the Facecraft app for server owners if the built in terminal. This lets you quickly and conveniently run commands on your Minecraft server from anywhere, just as if you are using the terminal directly. This is much more convenient than having to use SSH each time and can allow you to make sure your server is running smoothly without the hassle.

To use this feature, make sure you meet the following requirements:

- The Facecraft app is installed on your device
- You have registered a valid Facecraft account
- You have added your Facecraft account as an owner from the server terminal (as seen above)

If all that is done just:

1. Go into the app and login
2. Your Minecraft server should show up in your connections. Connect to it.
3. Enter the Server Console menu.
4. Here you will see all your previous server console messages. You will also be able to send new ones to be executed using the textbox and Send button.

Enjoy the wonderful convenience of Facecraft!