Black Box Testing: Equivalence Class and Boundary Value Testing

Control class tested: Percentage Match Estimator

Gross Floor Area (sqm)

Equivalence class partitioning:

| Invalid Partition | Valid Partition | Invalid Partition |
|--------------------------|--|---|
| • 0 • -1 • -2 • | 1249995000 | 500150025003 |

Boundary value testing:

| Invalid Partition - Valid Partition lower boundary | | Invalid Partition - Valid Partition Upper boundary | |
|--|------------------------------------|--|------------------------------------|
| Boundary Value just below boundary | Boundary Value just above boundary | Boundary Value just below boundary | Boundary Value just above boundary |
| 0 | 1 | 5000 | 5001 |

Room Count

Equivalence class partitioning:

| Invalid Partition | Valid Partition | Invalid Partition |
|--------------------------|---|-------------------|
| • 0 • -1 • -2 • | 1 2 3 4 5 | • 6 • 7 • |


Boundary value testing:

| Invalid Partition - Valid Partition lower boundary | | Invalid Partition - Valid Partition Upper boundary | |
|--|------------------------------------|--|------------------------------------|
| Boundary Value just below boundary | Boundary Value just above boundary | Boundary Value just below boundary | Boundary Value just above boundary |
| 0 | 1 | 5 | 6 |

Test Cases

| Test Input | Expected Output | Actual Output |
|--------------------------------|---|--|
| Input Gross Floor Area as 0 | Alert: Error, gross floor area can only be between 1 and 5000 sqm! | localhost:5173 says Error, gross floor area can only be between 1 and 5000 sqm! OK |
| Input Gross Floor Area as 1 | Lists of matching properties are generated successfully | Some Dead of South Control Listings |
| Input Gross Floor Area as 5000 | Lists of matching properties are generated successfully | Search Search Courted Cistings Courted Cistings |
| Input Gross Floor Area as 5001 | Alert: Error, gross floor area can only be between 1 and 5000 sqm! | localhost:5173 says Error, gross floor area can only be between 1 and 5000 sqml |
| Input Room Count as 0 | Such an option does not exist in the dropdown menu. Dropdown will thus default to empty state | Room Count Preferred number of rooms |
| Input Room Count as 1 | Dropdown option selected successfully | Room Count |
| Input Room Count as 5 | Dropdown option selected successfully | Room Count (§ |
| Input Room Count as 6 | Such an option does not exist in the dropdown menu. Dropdown will thus default to empty state | Room Count (Preferred number of rooms |

White Box Testing: Flowchart for Components: CurrentListing and LoginPage



Test Cases for CurrentListing function:

| Test Input | Expected Output | Actual Output |
|---|---|--|
| The user submits the desired property form and searches by clicking 'Search using my desired property attributes' | Able to view the attributes of the user's desired property | Search Location Tampines Amenities Select an option SEARCH OR Search using my desired property attributes Desired Property Location Tampines Select an option Select an opt |
| The user submits the desired property form and searches by clicking 'Search using my desired property attributes' | Able to view all the current listings | Current Listings Fig. 1 and 1 |
| The user submits the desired property form and searches by clicking 'Search using my desired property attributes' | Able to view the current listings with a percentage | PAGE TO 8 TREADER AT NAMES TREADER AT NAMES TREADER AT NAMES TREADER AT NAMES Tampines E2200000 Bit mass |
| The user searches using the 'Search' button | Should display all the current listings with the attributes matched | Current Listings The state of |

Test Cases for LoginPage function:

| Test Input | Expected Output | Actual Output |
|--|--|--|
| The user is authenticated (Successful) | Directed to the Homepage | Directed to the Homepage |
| The user is not authenticated (Unsuccessful) | Directed to Login Page | Directed to Login Page |
| Input Validation Valid Input and Password | Directed to the Homepage | localhost:5173 says login success nestling.ai |
| Input Validation Invalid Input and/or Password | Directed to Login Page | Welcome back! Wrong email/password Username nestling.al@gmail.com Password Forgot Password? |
| Clicked 'Forget Password' to reset password | Directed to forget password page to enter new password after clicking the verification email sent to the user's email | Log In via Email Enter email: Send log in link |