Keyboard Shortcuts

Selviana Desktop Environment 0.2.0 Alpha 4 · the shortcuts of Windows on SDE

Win is the key with the Windows logo (Super). **Ctrl+Alt+T**, **Ctrl+Alt+L** and SDE's other shortcuts still work.

Windows

Alt + F4	Close the active window; on the desktop, shut down or sign out
Alt + Space	Open the window menu (move, size, workspaces, always on top)
Alt + Tab	Switch to the next window (keep Alt down and press Tab again)
Alt + Shift + Tab	Switch to the previous window
Alt + Esc	Send the active window to the back and go to the next one
Win + Up	Maximize the window (a snapped half: its top quarter)
Win + Down	Restore a maximized or snapped window, or minimize it
Win + Left	Snap the window to the left half of the screen
Win + Right	Snap the window to the right half of the screen
Win + Shift + Up	Stretch the window to the top and bottom of the screen
Win + Shift + Down	Give the window its height back
Win + Shift + Left	Move the window to the monitor on the left
Win + Shift + Right	Move the window to the monitor on the right
Win + H	Minimize the active window
Win + M	Minimize all windows
Win + Shift + M	Restore the windows that Win+M minimized
Win + Home	Minimize all but the active window (again: restore them)
Win + D	Show the desktop, or the windows again

Workspaces and Task View

Win + Tab	Task View: every workspace and its windows
Ctrl + Alt + Tab	Task View to pick a window with the arrow keys and Enter
Ctrl + Win + D	Add a workspace and go to it (up to 5)
Ctrl + Win + F4	Close this workspace; its windows move to the one next to it
Ctrl + Win + Left *or* Ctrl + Alt + Left	Go to the workspace on the left
Ctrl + Win + Right *or* Ctrl + Alt + Right	Go to the workspace on the right
Ctrl + Win + Shift + Left *or* Ctrl + Alt + Shift + Left	Move the window to the workspace on the left, and go with it
Ctrl + Win + Shift + Right *or* Ctrl + Alt + Shift + Right	Move the window to the workspace on the right, and go with it

Start menu, search and apps

Win *or* Ctrl + Esc *or* Alt + F1	Open or close the Start menu
Win + S *or* Win + Q	Search for apps, files and settings
Win + R *or* Alt + F2	Run a command
Win + E	Open Liria, the file manager
Win + I	Open the Control Center
Win + A	Open the Action Center (quick settings)
Win + N	Show the notifications
Win + C *or* Win + Alt + D *or* Win + W	Show the calendar, agenda and weather
Win + X	Quick Link menu: apps, power, devices, Terminal, shut down or sign out
Ctrl + Alt + T	Open a terminal
Ctrl + Shift + Esc	Open System Monitor (the task manager)

Taskbar and system tray

Win + 1 … Win + 9	Open the app at that place on the taskbar, or switch to it
Win + Shift + 1 … Win + Shift + 9	Open another window of the app at that place on the taskbar
Win + T	Go through the taskbar buttons (arrows, Enter opens, Esc leaves)
Win + B	Open the system tray

Screenshots and emoji

PrtScn *or* Win + PrtScn	Screenshot of the whole screen, copied and saved
Alt + PrtScn	Screenshot of the active window, copied and saved
Win + Shift + S	Snip: drag an area, or pick a window or the whole screen
Win + . *or* Win + ;	Emoji picker (IBus)

Session, security and system

Ctrl + Alt + Delete	Security options: lock, switch user, sign out, task manager
Win + L *or* Ctrl + Alt + L	Lock the screen
Win + P	Display settings: monitors, arrangement and projection
Win + Pause	About this computer and SDE
Win + K	Connect Bluetooth devices
Win + Space	Next keyboard layout (Alt+Shift switches too)
Alt + Shift + F12	Turn the compositor (window effects) off or on
Ctrl + Win + Shift + B	Restart the compositor when the screen looks wrong

In SDE's applications

Ctrl + C	Copy Text fields, Liria, Niny, Xanara, Photo, Calculator
Ctrl + X	Cut Text fields, Liria, Niny, Xanara
Ctrl + V	Paste Text fields, Liria, Niny, Calculator, the desktop
Ctrl + Z	Undo Text fields, Liria, Niny, Xanara, Photo
Ctrl + Y or Ctrl + Shift + Z	Redo Ctrl+Y: Xanara; Ctrl+Shift+Z: Niny, Photo, Xanara
Ctrl + A	Select everything Text fields, Liria, Niny, Gallery, Taca
Ctrl + F	Find Liria, Niny, Xanara
Ctrl + N	New window, document or archive Liria, Niny, Photo, Gallery, Taca
Ctrl + O	Open a file Niny, Xanara, Photo, Gallery, Taca
Ctrl + S	Save Niny, Xanara, Photo
Ctrl + P	Print Niny, Xanara, Photo, Gallery
Ctrl + W	Close the tab or window Liria, Niny, Xanara, Photo, Taca
Ctrl + Q	Quit the application Liria, Niny, Xanara, Gallery, Taca
Ctrl + Tab or Ctrl + Shift + Tab	Next or previous tab Liria, Niny, Xanara
Ctrl + Plus or Ctrl + Minus or Ctrl + 0	Zoom in, out, or back to 100 % Liria, Niny, Xanara, Gallery
F1	About the application and its help SDE's programs
F2	Rename the selected file Liria, the desktop, Gallery, Taca
F5	Refresh Liria, the desktop, Gallery, Taca
F11	Full screen Liria, Niny, Xanara, Photo, Gallery
Shift + F10 or Menu	Open the context menu Liria, Niny, the desktop, Gallery, Taca, the Start menu
Alt + Enter	Properties of the selected file Liria
Delete or Shift + Delete	Move to the trash; with Shift, delete for good Liria, the desktop
Alt + Left or Alt + Right or Alt + Up	Back, forward, up one folder Liria
Ctrl + L	Type a location Liria
Ctrl + Shift + N	New folder Liria, the desktop
Esc	Cancel, or close a dialog or menu Everywhere

With the mouse

Right click on a title bar, or a click on the window's icon	The window menu
Double click on a title bar	Maximize or restore
Alt + drag	Move a window from anywhere in it
Alt + right drag	Resize a window
Middle click on a title bar	Send the window to the back
Right click on a taskbar button	The window's menu, with the app's own items
Right click on the Start button	The Quick Link menu (as Win+X)

Not available in SDE

Win + V	**Clipboard history** Not yet: SDE has no clipboard history. Ctrl+V pastes the last copy
Win + Plus or Win + Minus or Win + Esc	**Magnifier** Not yet: the compositor cannot zoom the screen
Win + G	**Game Bar** Not available
Win + U	**Accessibility settings** Not available yet: text size and scale are in Control Center > Appearance
Win + Ctrl + Enter	**Narrator** Not available: start the Orca screen reader from the Start menu when it is installed
Win + Ctrl + O	**On-screen keyboard** Not available: start Onboard from the Start menu when it is installed
Win + F	**Feedback Hub** Not available
Win + Z	**Snap layouts** Not available: use Win+Left, Win+Right, Win+Up and Win+Down
Win + Comma	**Peek at the desktop** Not available: Win+D shows the desktop

Win+H is voice typing on Windows; SDE has no dictation, and Win+H minimizes the active window as it always has on SDE.

Changing a shortcut

In `~/.config/sde/sde.conf`, `[shortcuts]` gives a shortcut other keys (`W-` Win, `C-` Ctrl, `A-` Alt, `S-` Shift; `none` turns it off), e.g. `terminal=C-A-t W-Return`. `sde-windows shortcuts` lists the names. The whole guide: `/usr/share/doc/sde/SHORTCUTS.md`.