

Linux perusteet [TTC1040]

harjoitus 1



Maarit Salo

1.9.2021

1. Machine name

```
user@P0033-Ubuntu:~$ uname -m
x86_64
```

2. Kernel name, version and release

```
user@P0033-Ubuntu:~$ uname --kernel-name -r -v
Linux 5.4.0-81-generic #91-Ubuntu SMP Thu Jul 15 19:09:17 UTC 2021
```

3. Version of uname command

```
user@P0033-Ubuntu:~$ uname --version
uname (GNU coreutils) 8.30
Copyright (C) 2018 Free Software Foundation, Inc.
License GPLv3+: GNU GPL version 3 or later <a href="https://gnu.org/licenses/gpl.html">https://gnu.org/licenses/gpl.html</a>.
This is free software: you are free to change and redistribute it.
There is NO WARRANTY, to the extent permitted by law.
Written by David MacKenzie.
```

4. System memory amount (GiB)

```
user@P0033-Ubuntu:~$ lshw -class memory
WARNING: you should run this program as super-user.

*-memory
description: System memory
physical id: 0
size: 1GiB
WARNING: output may be incomplete or inaccurate, you should run this program as super-user.
```

5. Processor

```
user@P0033-Ubuntu:~$ uname -p x86 64
```

6. Display adapter

```
user@P0033-Ubuntu:~$ sudo lshw -c display
  *-display
  description: VGA compatible controller
  product: SVGA II Adapter
  vendor: VMware
  physical id: f
  bus info: pci@0000:00:0f.0
  version: 00
  width: 32 bits
  clock: 33MHz
  capabilities: vga_controller bus_master cap_list rom
  configuration: driver=vmwgfx latency=64
  resources: irq:l6 ioport:1070(size=16) memory:e8000000-efffffff memory:fe000000-fe7fffff memory:c0000-dffff
```

7. Distribution release and description

user@P0033-Ubuntu:~\$ lsb_release -r -d
Description: Ubuntu 20.04.3 LTS
Release: 20.04

8. Codename of the distribution

user@P0033-Ubuntu:~\$ lsb_release -c Codename: focal_