



CA Manual Valve System v1.0

The Manual Valve System is a tool that allows you to make any rotatable object into a manually interactable valve. Turning the valve will allow for some realistic results like slowly open a heavy gate or turn off steam leaks from a pipe etc.

If you have any questions or concerns
please contact me via chillasart@gmail.com

Contents of this asset:

Scripts:

- Manual Valve Script
- Raycast Interact Manager Script
- Valve Gate Script
- Min Max Activation Script


Sounds:

- Valve turn sound
- Gate sound
- Steam leak sound

3d Models/Extra assets:

- Valve model
- Steam particle
- Hand icons
- Sample first person player script

The Manual Valve Script



Player setup:

Note that if you have a custom controller, disable and enable your custom controller in the script's **DisableLook()** and **EnableLook()** methods.

Below is the example of using the sample player look script.


```
208 1 reference
209 void DisableLook()
210 {
211     //put your own player controller script to disable here
212     interactManager.GetComponent<CA_Sample_PlayerLook>().enabled = false;
213 }
214 2 references
215 void EnableLook()
216 {
217     // put your own player controller script to enable here
218     interactManager.GetComponent<CA_Sample_PlayerLook>().enabled = true;
219 }
```

Valve Setup:


Handle - insert a game object that will act as a handle and it will be where the force will be added. This is also where the hand icons will be at.

Forward Axis Type – In this example, it will be z.

Right Axis Type – In this example, it will be x.




Icons Setup:



Make sure that they are under the Handle game object you created for valve set up. See the demo scene for how the Icons are disabled and enabled.

Min&Max Settings:



Set up spheres to block on Max and Min value and insert them on appropriate slots. You can also make them lock when they reach the min or max point.

In the demo MinMaxValue is set at -1000 and 0, but if you want the valve to turn counter-clockwise, you can make it 0 to 1000 or even lower the values so you don't have to rotate it as much.


Refer to the demo scene to see how the rotation values change.

Blocker cube:

As you can see in the image, there is a blocker cube in the middle.


To set that up, you need to attach a Rigidbody and a fixed joint to a cube. Then, make sure to connect the valve to the fixed joint.

Raycast Interact Manager Script



This is a raycast based interact manager script. Attach this to your player camera.

Valve Gate Script




Insert any valve in the scene into the valve GameObject slot.

The Move Axis Type is the direction of the gate movement. (i.e.. A gate that moves up and down is 'Y')

Strength is how far the gate will move. Smooth Time is how smooth the gate moves.

Min Max Activation Script

If you check out the demo scene, you'll find a couple of valves disabling and enabling a steam. This is how it's doing that. It is simply enabling and disabling when the min and max block spheres appear.



You can set any GameObject or any component to disable or enable whenever min and max blockers get enabled. So attach this script to both min and max blockers for this to work.