CSE3151

COMPUTER NETWORKS



Dr. Asif Zaman

ASSOCIATE PROFESSOR, CSE, RU

April 19, 2018

NETWORK LAYER

Medium Access Sublayer: Pure and slotted ALOHA, Persistent and Non persistent CSMA, CSMA with collision detection and collision free protocols, IEEE standard 802.3 and Ethernet.

Data Link Layer: Types of errors, framing, error detection & correction methods; Flow control, Stop & wait ARQ, Go-Back- N ARQ, Selective repeat ARQ, HDLC.

Network Layer: Internet address, classful address, subnetting, static vs. dynamic routing, shortest path algorithm, flooding, distance vector routing, link state routing, ARP, RARP, IP, ICMP.


Transport Layer: UDP, TCP, Connection management, Addressing, Establishing and Releasing Connection Congestion control algorithm. Flow control and Buffering. Multiplexing.

Presentation Layer: Data Compression techniques, Frequency Dependent Coding, Context Dependent

2 of 12


ROUTING

- The main function of the network layer is **ROUTING PACKETS** from the source machine to the destination machine.
- In most networks, packets will require multiple hops to make the journey.
 - The routing algorithm is that part of the network layer software responsible for deciding which output line an incoming packet should be transmitted on.
- ROUTING ALGORITHMS can be grouped into two major classes:
 - NONADAPTIVE AND
 - ADAPTIVE.



NONADAPTIVE ROUTING

- NONADAPTIVE algorithms do not base their routing decisions on any measurements or estimates of the current topology and traffic
- Instead, the choice of the route to use to get from I to J (for all I and J) is computed in advance, offline, and downloaded to the routers when the network is booted.
- This procedure is sometimes called static routing



4 of 12


ADAPTIVE ROUTING

- ADAPTIVE algorithms, in contrast, change their routing decisions to reflect changes in the topology, and sometimes changes in the traffic as well.
- These dynamic routing algorithms differ in :
 - where they get their information (e.g., locally, from adjacent routers, or from all routers),
 - when they change the routes (e.g., when the topology changes, or every ΔT seconds as the load changes), and
 - what metric is used for optimization (e.g., distance, number of hops, or estimated transit time

5 of 12


OPTIMALITY PRINCIPLE

 It states that if router J is on the optimal path from router I to router K then the optimal path from J to K also falls along the same route



6 of 12

THE SHORTEST PATH ALGORITHM




- One way of measuring path length is the number of hops.
 Using this metric, the paths ABC and ABE in Fig. 5-7 are equally long.
- Another metric is the geographic distance in kilometers, in which case ABC is clearly much longer than ABE.
- Dijkstra

7 of 12

FLOODING

- When a routing algorithm is implemented, each router must make decisions based on local knowledge, not the complete picture of the network.
- A simple local technique is flooding, in which every incoming packet is sent out on every outgoing line except the one it arrived




8 of 12

DISTANCE VECTOR ROUTING

- A distance vector routing algorithm operates by having each router maintain a table (i.e., a vector) giving the best known distance to each destination and which link to use to get there
- These tables are updated by exchanging information with the neighbors. Eventually, every router knows the best link to reach each destination
- As an example, assume that delay is used as a metric and that the router knows the delay to each of its neighbors

9 of 12



LINK STATE ROUTING

- 1. Discover its neighbors and learn their network addresses.
- 2. Set the distance or cost metric to each of its neighbors.
- 3. Construct a packet telling all it has just learned.
- 4. Send this packet to and receive packets from all other routers.
- 5. Compute the shortest path to every other router.

11 of 12

ARP and RARP

- Address Resolution Protocol
- Reverse Address Resolution Protocol



12 /