PCSDA SECURE NETWORK ACCESS REQUEST

FORM IR-1

Please complete this form to request access to the PCSDA Church or School secure network.
Authorized access is required for all personal and non-organization devices.

1. REQUESTOR INFORMATION

Full Name:	
Role / Affiliation:	☐ Staff / Teacher ☐ Church Member ☐ Student ☐ Guest / Vendor
Email Address:	
Phone Number:	

2. DEVICE INFORMATION

Device Type:	*(e.g., iPhone 14, Windows 11 Laptop, iPad)*
Device Ownership:	☐ Personal Device ☐ PCSDA Owned Device
WiFi MAC Address(es):	*(e.g., A1:B2:C3:D4:E5:F6) — See Appendix on back*

3. ACCESS JUSTIFICATION

Why do you need access to the PCSDA Secure Network?

_____

_____

Duration of Access:

☐ Permanent / Ongoing ☐ Temporary (End Date:)

4. ACCEPTABLE USE AGREEMENT

- I agree to use the PCSDA network strictly for authorized educational, ministry, or administrative purposes.
- I will not attempt to bypass security controls, access unauthorized network segments, or distribute malicious software.
- I understand that network traffic on the secure network may be monitored for security and performance purposes.

5. SIGNATURES

Requestor Signature: _____ **Date:** _____

Approver / Sponsor: _____ **Date:** _____

IT Admin Approval: _____ **Date:** _____

APPENDIX: HOW TO FIND YOUR WIFI MAC ADDRESS

The MAC (Media Access Control) address is a unique 12-character identifier for your device's WiFi antenna. We need this to allow your specific device through the firewall.

> **CRITICAL NOTE ON MAC RANDOMIZATION:**
> Modern phones use a privacy feature that changes your MAC address depending on the network. To maintain access to the PCSDA network, you **MUST turn off "Private Wi-Fi Address" (Apple) or "MAC Randomization" (Android)** specifically for the PCSDA WiFi connection, otherwise you will lose access the next time you connect.

Apple iOS (iPhone / iPad)

1. Open the **Settings** app (gear icon).
2. Tap on **General**, then tap on **About**.
3. Scroll down to find the **Wi-Fi Address** field.

Windows Laptop

1. Click the Start button, type **cmd**, and press Enter.
2. Type `ipconfig /all` and press Enter.
3. Look for **Wireless LAN adapter Wi-Fi**.
4. Find the **Physical Address**.

Android Devices

Steps vary slightly by manufacturer.

1. Open the **Settings** app.
2. Scroll down and tap **About Phone**.
3. Tap **Status information**.
4. Locate the **Wi-Fi MAC address**.

MacBook (macOS)

1. Click the Apple menu (t) and select **System Settings**.
2. Click on **Network**, then select **Wi-Fi**.
3. Click **Advanced** or **Details**.
4. Look for the **Wi-Fi MAC Address**.

TURN OFF PRIVATE / RANDOM MAC FOR PCSDA WI-FI

Do this while connected to (or after joining) the PCSDA Wi-Fi, then read the device's real MAC and write it on the form. After changing the setting, **disconnect and reconnect** (or **Forget** the network and rejoin) so the network sees the real address.

iPhone / iPad (iOS / iPadOS 18+)

1. **Settings > Wi-Fi**, tap the **(i)** next to PCSDA.
2. **Private Wi-Fi Address** > **Off** (older iOS: toggle off).
3. Tap **Rejoin** / **Continue** if prompted.

Real MAC: Settings > General > About > **Wi-Fi Address**.

Windows 11 (Windows 10 similar)

1. **Settings > Network & internet > Wi-Fi**.
2. Turn **Random hardware addresses Off** (global).
3. Open **PCSDA properties** > **Random hardware addresses** > **Off**.
4. Disconnect and reconnect to PCSDA.

Win 10: Settings > Network & Internet > Wi-Fi > same toggles (or Manage known networks > PCSDA > Properties).

Real MAC: ipconfig /all > Wireless LAN adapter Wi-Fi > **Physical Address**.

Android

Samsung (One UI): Settings > Connections > Wi-Fi > gear by PCSDA > View more > **MAC address type** > **Phone MAC**.

Pixel / stock: Settings > Network & internet > Internet > gear by PCSDA > **Privacy** > **Use device MAC**.

Then reconnect to PCSDA. Other brands: look for Privacy or MAC address type in the network's settings.

Real MAC: Settings > About phone (> Status information) > **Wi-Fi MAC address**.

Mac (macOS Sonoma / Sequoia+)

1. **System Settings > Wi-Fi**.
2. Click **Details** next to PCSDA.
3. **Private Wi-Fi address > Off**, then **OK**.
4. Turn Wi-Fi off and back on to reconnect.

Real MAC: same Details pane > **MAC address** (with Private off), or Option-click the Wi-Fi menu icon > **Address**.