This integration allows one to capture log entries from an integrations server for viewing and troubleshooting. This capability avoids the need to manually access and collect the logs.

### **Key Features**

- filter logs by date (before or after a specified date and time)
- filter logs entries by number of log entries to return (ex. last 1000 lines)
- filter by minimum log level: DEBUG, INFO, WARNING and ERROR

# fn-log-capture Functions for IBM Resilient

- Release Notes
- Overview
- Requirements
- Installation
- Uninstall
- Troubleshooting
- Support


### Release Notes

#### v1.0.0

• Initial Release

### Overview

Resilient Circuits Components for 'fn\_log\_capture



# Requirements

- Resilient platform >= v32.0.4502
- An Integration Server running resilient\_circuits>=30.0.0
  - To set up an Integration Server see: ibm.biz/res-int-server-guide

## Installation

- Download the fn\_log\_capture.zip.
- Copy the .zip to your Integration Server and SSH into it.
- **Unzip** the package:

```
$ unzip fn_log_capture-x.x.x.zip
```

• Change Directory into the unzipped directory:

```
$ cd fn_log_capture-x.x.x
```

• Install the package:

```
$ pip install fn_log_capture-x.x.x.tar.gz
```

• Import the fn\_log\_capture **customizations** into the Resilient platform:

```
$ resilient-circuits customize -y -l fn-log-capture
```

• [Optional]: Run selftest to test the Integration you configured:

```
$ resilient-circuits selftest -l fn-log-capture
```

• Run resilient-circuits or restart the Service on Windows/Linux:

```
$ resilient-circuits run
```

## Uninstall

- SSH into your Integration Server.
- Uninstall the package:

```
$ pip uninstall fn-log-capture
```

2019-10-27

2/3

## **Troubleshooting**

There are several ways to verify the successful operation of a function.

#### **Resilient Action Status**

- When viewing an incident, use the Actions menu to view Action Status.
- By default, pending and errors are displayed.
- Modify the filter for actions to also show Completed actions.
- Clicking on an action displays additional information on the progress made or what error occurred.

### **Resilient Scripting Log**

- A separate log file is available to review scripting errors.
- This is useful when issues occur in the pre-processing or post-processing scripts.
- The default location for this log file is: /var/log/resilient-scripting/resilientscripting.log.

### **Resilient Logs**

- By default, Resilient logs are retained at /usr/share/co3/logs.
- The client.log may contain additional information regarding the execution of functions.

#### **Resilient-Circuits**

- The log is controlled in the .resilient/app.config file under the section [resilient] and the property logdir.
- The default file name is app.log.
- Each function will create progress information.
- Failures will show up as errors and may contain python trace statements.

No additional configuration required.

# Support

Name	Version	Author	Support URL
fn_log_capture	1.0.0	IBM Resilient	support@resilientsystems.com

2019-10-27

3/3