

**RE: SRT GW for testing**

From Aleksander Šibila <asi@ikomg.com>

Date Thu 20 Aug 2026 12:45

To Izik Ezra <ie@ikomg.com>; Adir Hadad <ah@ikomg.com>

Cc Nadav Maman <nm@ikomg.com>; Vittorio Mennella <vme@ikomg.com>; Valentin Mrak <vm@ikomg.com>; Rytenis Serenas <rs@ikomg.com>

Hi Izik and Adir,

Some screenshots 😊

Default page when you start adding the route:

Focus on INPUT side!

Protocol Menu:

Here becomes tricky as further menus and fields are shown dynamically:

For UDP:

Network Interface

Auto

Auto

ens160

ens192

ens224

If TS over SRT is selected in Listener mode:

Source Name *

New Source

Protocol

TS Over SRT

Type

Listener

Listener

Caller

Rendezvous

Network Interface

Auto

Address *

000.000.000.000

Port *

0000

SRT Parameters

Latency (20-8000)

125

Receive Buffer (kb)

10240

Passphrase

In caller mode is a bit different:

Source

Source Name *

New Source

Protocol

TS Over SRT

Type

Caller

Network Interface

Auto

Address *

000.000.000.000

Port *

0000

SRT Parameters

Latency (20-8000)

125

Receive Buffer (kb)

10240

Passphrase

Stream ID

Enter Stream ID

Error Correction Method

ARQ

ARQ

FEC

FEC + ARQ

In case of path redundancy you will get additional row for selecting Network interface, address and port.

Under stream ID you get the following options if default stream id format is selected:

Network Interface

Auto

Address

0000000000000000

Edit Stream

Stream ID Format

☒ Default ☐ Custom

RES Name

Resource Name

CANCEL

Enter Stream ID

In case of Custom Stream ID format:

Network Interface

Auto

Address

0000000000000000

Edit S

Stream ID Format

☐ Default ☒ Custom

Stream ID

#!-u="haivision",h=

CANCEL

Focus on DESTINATION!

Default screen for UDP out:

ADD DESTINATION

×

Destination Name *

New Destination

Protocol

TS Over UDP

Network Interface

Auto

Address *

000.000.000.000

Port *

0000

Link Parameters

FEC

None

Max. Bitrate (kbps)

10,000

☐ Traffic Shaping

MTU (280 - 1500)

1496

TTL (1 - 255)

64

ToS (0x00 - 0xFF)

0xBB

☒ Start Once Route Starts

SAVE

Screen for SRT out in listener mode:

ADD DESTINATION

Destination Name *

New Destination

Protocol

TS Over SRT

Type

Listener

Path Redundancy Mode ?

None

Connection Limit

None

Number of Callers *

10

Network Interface

Auto

Address *

000.000.000.000

Port *

0000

Link Parameters

MTU (280 - 1500)

1496

TTL (1 - 255)

64

ToS (0x00 - 0xFF)

0x68

SRT Parameters

Latency (20-8000)

125

Retransmission Bandwidth (1-1000000kbps) ?

RTP Header

None

Encryption

None

Passphrase *

Authentication

Auto

☒ Start Once Route Starts

SAVE

Screen for SRT out in caller mode:

about:blank?windowId=SecondaryReadingPane20

4/6

ADD DESTINATION

Destination Name *

New Destination

Protocol

TS Over SRT

Type

Caller

Path Redundancy Mode ?

None

Network Interface

Auto

Address *

172.16.93.171

Port *

0000

Link Parameters

MTU (280 - 1500)

1496

TTL (1 - 255)

64

ToS (0x00 - 0xFF)

0x68

SRT Parameters

Latency (20-8000)

125

Retransmission Bandwidth (1-1000000kbps) ?

Encryption

None

Passphrase

Authentication

None

Stream ID

Enter Stream ID

RTP Header

None

Error Correction Method ?

ARQ

☒ Start Once Route Starts

SAVE

StreamID settings – actually same fields as for input:

Edit Stream ID

Stream ID Format

☒ Default ☐ Custom

Host & Mode

h=172.16.93.171,m=publish

RES Name

Resource Name

User Name

User Name

CANCEL

APPLY

Enter Stream ID

I hope it helps, in other case we can go trough togeteather.

Best regards,
Aleksander
--

**ALEKSANDER ŠIBILA**
VP ENGINEERING

Kidričeva Ulica 22/A, SI-1233 Dob, Slovenia
+386 1 527 2461
+386 51 273 319
asi@ikomg.com
www.ikomg.com

From: Izik Ezra <ie@ikomg.com>

Sent: Tuesday, 18 August 2026 16:45

To: Adir Hadad <ah@ikomg.com>; Valentin Mrak <vm@ikomg.com>; Aleksander Šibila <asi@ikomg.com>; Rytenis Serenas <rs@ikomg.com>

Cc: Nadav Maman <nm@ikomg.com>; Vittorio Mennella <vme@ikomg.com>

Subject: RE: SRT GW for testing

Hi guys,

As we discussed, please share with Adair some screenshots, examples, or details of the fields required for our new SRT Gateway so he can adjust the interface as needed and start testing.

To begin with, I suggest we include the following capabilities for the input and output configuration:

- Ability to select the protocol.
- Destination IP address.
- Multicast or unicast selection, where applicable.
- Port configuration for both input and output.
- Ability to associate each configured IP address/stream with a specific NIC available on the server.

Separately, under a **Network** menu, we would like to have the ability to configure or change the IP settings for each NIC available on the machine. These network settings should be applied directly to the Linux Netplan configuration so that the configuration remains persistent on the server.

In a second stage, we also plan to use these servers for basic transcoding and packaging. Therefore, while defining the UI and architecture, please keep these future capabilities in mind.

Even if transcoding and packaging are not part of the first release, we should try to structure the system in a modular way so these functions can be added later without requiring major changes to the existing gateway configuration and workflow.

Please share any additional fields, screenshots, or requirements you think should be included so we can finalize the initial configuration and begin testing.

Thank you!

**IZIK EZRA**
SVP ENGINEERING

Via Cornelia, 498 - 00166, Rome, Italy
+39 349 356 9902
ie@ikomg.com
www.ikomg.com

From: Adir Hadad <ah@ikomg.com>

Sent: Tuesday, 11 August 2026 16:43

To: Valentin Mrak <vm@ikomg.com>; Izik Ezra <ie@ikomg.com>; Aleksander Šibila <asi@ikomg.com>; Rytenis Serenas <rs@ikomg.com>

Subject: SRT GW for testing

Hi guys,

Please find the attached UM for the SRT GW.

You can access the service on:

SRT GW UI - [SRT Web Gateway](#)

SRT Server Monitoring - [Home - Dashboards - Grafana](#) (admin/admin)

Please take some time to play around set up streams and report on issues that you find.

Thanks,
Adir