Windows

Focus, move, resize, float

Meta+L focuses right. Use Meta+Alt+L to lock.

Focus and switch

`Meta + H / J / K / L`	Focus left / down / up / right.
`Meta + arrows`	Focus in that direction.
`Meta + Alt + arrows`	Alternative directional focus.
`Alt + Tab / Meta + Tab`	Cycle windows on this desktop.
`Add Shift to either Tab chord`	Cycle windows backward.
`Alt + ` / Meta + `	Cycle windows of the same app.
`Add Shift to either ` chord`	Cycle same-app windows backward.

Move and resize

`Meta + Shift + arrows`	Move the window in that direction.
`Meta + Ctrl + H/J/K/L` `or Meta + Ctrl + arrows`	Resize by 20 px; hold to repeat.
`Meta + left-drag`	Drag the window.
`Meta + right-drag`	Resize. Floats first only if it is the sole window on this desktop.
`Meta + X`	Start resizing with the mouse.

Window state

`Meta + I / Meta + Alt + F10`	Toggle floating.
`Meta + F`	Toggle fullscreen.
`Meta + Alt + F / Meta + PgUp`	Toggle maximized.
`Meta + PgDown`	Minimize the active window.
`Meta + Backspace`	Restore all minimized windows to their original desktops.
`Meta + D`	Show desktop; press again to restore.
`Meta + P`	Toggle pinning across desktops.
`Meta + W / Alt + F4`	Close the active window.

Desktops & apps

Your number keys select desktops

Spotify hides in the music workspace. Meta+M brings it back.

Virtual desktops

`Meta + 1…9 / 0`	Go to desktop 1…10 in this group. Zero means 10.
`Meta + Shift + 1…9 / 0`	Move the window to that desktop.
`Ctrl + F1…F4 / Meta + F1…F4`	Go directly to desktop 1…4.
`Meta + wheel up / down`	Previous / next desktop.
`Meta + Ctrl + Shift + ← / ↑`	Move window to the previous desktop.
`Meta + Ctrl + Shift + → / ↓`	Move window to the next desktop.

Launch your apps

`Meta, press and release`	Open the app launcher.
`Meta + R / Meta + Space`	Open the app launcher.
`Alt + Space / Alt + F2 or Search key`	Alternative launcher shortcuts.
`Meta + Enter / Meta + T`	Open WezTerm.
`Meta + Alt + Enter`	Open Foot.
`Meta + B / E / C / Z`	Brave / Dolphin / VSCodium / ROG Control Center, respectively.
`Ctrl + Alt + V`	Open audio settings.

Hidden / special desktops

`Meta + S`	Show / hide the general special workspace.
`Meta + M`	Show / hide the music workspace.
`Meta + Alt + D`	Show / hide the communication workspace.
`Ctrl + Shift + Esc`	Show / hide the system monitor workspace.
`Meta + Alt + S`	Move window into the general special workspace.
`Meta + Ctrl + Alt + S`	Move window out to the active normal desktop.

Capture & appearance

Screenshots, recordings, wallpaper, clipboard

Meta+Shift+S takes a screenshot. Meta+S opens the special workspace.

Screenshots and recordings

`Print Screen`	Take a screenshot.
`Meta + Shift + S`	Freeze the screen and select a screenshot region.
`Ctrl + Shift + S` `or Meta + Alt + Shift + S`	Select a screenshot region.
`Ctrl + Alt + R`	Start / stop a fullscreen recording.
`Meta + Alt + R`	Start / stop recording with sound.
`Meta + Shift + R` `or Meta + Alt + Shift + R`	Start / stop a region recording.
`Meta + Shift + C`	Pick a screen color and copy its hex value.

Wallpaper and theme

`Meta + Alt + W`	Open the wallpaper picker.
`Meta + Shift + W`	Choose a random wallpaper.
`Launcher: wa`	Find wallpapers without typing the full word.
`Launcher: th / sc`	Find themes / color schemes.
`Tab in the launcher`	Complete the wallpaper or theme keyword.
`Launcher: wallpaper forest`	Filter wallpapers by their names.

Clipboard and emoji

`Meta + V`	Open clipboard history.
`Meta + Alt + V`	Open clipboard history in delete mode.
`Ctrl + Alt + Shift + V`	Paste the newest clipboard entry.
`Meta + .`	Open the emoji picker.

Media & gestures

Sound, light, touchpad

Hold Shift with volume or screen-brightness keys for fine 1% steps.

Music and sound

`Play / Pause media keys`	Toggle playback.
`Meta + Ctrl + Space`	Toggle playback from the keyboard.
`Next / Previous media keys`	Skip to the next / previous track.
`Meta + Ctrl + = / -`	Next / previous track.
`Stop media key` `or Meta + Ctrl + Backspace`	Stop playback.
`Mute key / Meta + Shift + M`	Toggle output mute.
`Microphone mute key`	Toggle microphone mute.
`Volume up / down keys`	Change output volume by 10%.
`Shift + volume keys`	Change output volume by 1%.

Brightness

`Screen-brightness keys`	Raise / lower screen brightness.
`Shift + screen-brightness keys`	Raise / lower brightness by 1%.
`Keyboard-brightness keys`	Raise / lower keyboard backlight.

Touchpad gestures

`3 fingers ← / →`	Slide between virtual desktops.
`3 fingers ↑ / ↓`	Show / hide the general special workspace.
`4 fingers ↓`	Suspend, then hibernate.

Sleep hardware keys

`Sleep key`	Suspend.
`Hibernate key`	Hibernate.

Panels & advanced

Shell controls, groups, layout

Stop shell hides the panels. Use Restart shell to bring them back.

Panels and session

`Meta + N`	Toggle the sidebar.
`Meta + Alt + K`	Toggle shell panels.
`Ctrl + Alt + C`	Clear notifications.
`Meta + Alt + L`	Lock the screen.
`Ctrl + Alt + Delete`	Open the session / power menu.
`Meta + Shift + L`	Suspend, then hibernate.
`Meta + Ctrl + Alt + L`	Start the shell if needed and request a lock.
`Meta + Ctrl + Alt + R`	Restart the Caelestia shell; runs on release.
`Meta + Ctrl + Shift + R`	Stop the Caelestia shell; runs on release.
`Meta + Alt + F12`	Send a test notification.

Window groups

`Meta + ,`	Toggle a window group.
`Meta + Shift + ,`	Toggle the active group lock.
`Meta + U`	Move the window out of its group.
`Ctrl + Alt + Tab`	Next window in the group.
`Ctrl + Alt + Shift + Tab`	Previous window in the group.

Layout and workspace groups

`Meta + Ctrl + \`	Center the window.
`Meta + Ctrl + Alt + \`	Size to 55% × 70% of the screen, then center.
`Meta + Alt + \`	Picture-in-picture: float, pin and resize.
`Meta + Ctrl + Alt + - / =`	Decrease / increase window width.
`Meta + Ctrl + Shift + - / =`	Decrease / increase window height.
`Meta + Ctrl + wheel ↑ / ↓`	Previous / next workspace group (±10).
`Meta + Ctrl + Alt + 1…9 / 0`	Jump to workspace group 1…10.
`Add Shift to group numbers`	Move window to that workspace group.

Launcher & terminal

Search commands and your shell conveniences

Type a launcher command, choose its result, then press Enter to run it.

Launcher controls and power commands

`↑ / ↓ · Enter · Esc`	Select a result · open it · close launcher.
`Tab`	Complete the selected command keyword.
`>`	Browse launcher actions; >calc opens calculator.
`shutdown / power off / turn off`	Shut down the computer.
`reboot / restart`	Restart the computer.
`logout / log out / sign out`	Log out of this session.
`lock / lock screen`	Lock this session.
`sleep / suspend / hibernate`	Sleep uses suspend-then-hibernate; the others request their named modes.
`>light / >dark / >variant`	Choose light, dark or a palette variant.

Fish and zoxide

`cd name / z name`	Use a path or jump to a remembered directory.
`cdi / zi`	Pick a remembered directory interactively.
`↑ / ↓ after typing`	Search command history by the typed prefix.
`Ctrl + F`	Accept the autosuggestion.
`Ctrl + W / Ctrl + D`	Delete the previous word / delete or exit.
`Ctrl + ← / →`	Move backward / forward by one word.
`.. / ...`	Expand to cd .. / cd ../..
`ll / la / lt · cat · top`	Detailed / all / tree listings · bat · btop.
`gs / gd / gl / lg`	Git status / diff / graph / lazygit.
`reload · pipapp`	Reload Fish config · manage Python CLI apps through pipx.

Terminal-specific controls

`WezTerm: Shift + Enter`	Send the alternate Enter sequence (Esc + Enter).
`Foot: PgUp / PgDown`	Scroll one page up / down.
`Foot: Ctrl + Shift + F`	Search scrollback.
`Foot search: F3 / Ctrl + G`	Next match; Shift+F3 goes to previous match.
`Foot search: Esc`	Leave scrollback search.