

I am using a

```
conda config --show subdir
subdir: osx-arm64
```

Which caused conflicts with tensor flow. I ran (based on Chatgpt):

```
conda config --env --set subdir osx-64
```

But need to check

<https://stackoverflow.com/questions/65415996/how-to-specify-the-architecture-or-platform-for-a-new-conda-environment-apple>. I don't want to run into issues with arm and osx 64 in miniconda later on.

Following this instead to install scaden.

<https://medium.com/@lorenzozar/how-to-install-rosetta-on-mac-53c74391d2f5>

```
curl -L -O "https://github.com/conda-forge/miniforge/releases/latest/download/Miniforge3-MacOSX-arm64.sh"
```

```
sh Miniforge3-MacOSX-arm64.sh
```

Transaction finished

installation finished.

Do you wish to update your shell profile to automatically initialize conda?

This will activate conda on startup and change the command prompt when activated.

If you'd prefer that conda's base environment not be activated on startup,

run the following command when conda is activated:

```
conda config --set auto_activate_base false
```

You can undo this by running `conda init --reverse \$SHELL`? [yes|no]

[no] >>> yes

```
no change      /Users/nv4/miniforge3/condabin/conda
no change      /Users/nv4/miniforge3/bin/conda
no change      /Users/nv4/miniforge3/bin/conda-env
no change      /Users/nv4/miniforge3/bin/activate
no change      /Users/nv4/miniforge3/bin/deactivate
no change      /Users/nv4/miniforge3/etc/profile.d/conda.sh
no change      /Users/nv4/miniforge3/etc/fish/conf.d/conda.fish
no change      /Users/nv4/miniforge3/shell/condabin/Conda.psm1
no change      /Users/nv4/miniforge3/shell/condabin/conda-hook.ps1
no change      /Users/nv4/miniforge3/lib/python3.12/site-packages/
xontrib/conda.xsh
no change      /Users/nv4/miniforge3/etc/profile.d/conda.csh
```

modified /Users/nv4/.zshrc

==> For changes to take effect, close and re-open your current shell. <==

Running `shell init`, which:

- modifies RC file: "/Users/nv4/.zshrc"
- generates config for root prefix: "**/Users/nv4/miniforge3**"
- sets mamba executable to: "**/Users/nv4/miniforge3/bin/mamba**"

The following has been added in your "/Users/nv4/.zshrc" file

```
# >>> mamba initialize >>>
# !! Contents within this block are managed by 'mamba shell init' !!
export MAMBA_EXE='/Users/nv4/miniforge3/bin/mamba';
export MAMBA_ROOT_PREFIX='/Users/nv4/miniforge3';
__mamba_setup="$("$MAMBA_EXE" shell hook --shell zsh --root-prefix
"$MAMBA_ROOT_PREFIX" 2> /dev/null)"
if [ $? -eq 0 ]; then
    eval "$__mamba_setup"
else
    alias mamba="$MAMBA_EXE" # Fallback on help from mamba activate
fi
unset __mamba_setup
# <<< mamba initialize <<<
```

Thank you for installing Miniforge3!

- Code above changed the base to miniforge iso miniconda!!!

- Now add this to `~/.zshrc`

```
# Create x86 conda environment
create_x86_conda_environment () {

    # example usage: create_x86_conda_environment
    myenv_x86 python=3.9
    CONDA_SUBDIR=osx-64 conda create -n $@
    conda activate $1

}

# Create ARM conda environment
create_ARM_conda_environment () {

    # example usage: create_ARM_conda_environment
    myenv_x86 python=3.9
    CONDA_SUBDIR=osx-arm64 conda create -n $@
    conda activate $1

}
```

- I want to create an osx-64 (x86_64)

```
create_x86_conda_environment scadenEnvX86 python=3.8
```

This way, it is not overriding my default arm. Note, the default Conda now comes from mini forge rather than miniconda.

```
pip install scaden==0.9.4
```