# ESO 208A: Computational Methods in Engineering

### Richa Ojha

Department of Civil Engineering IIT Kanpur



#### Copyright:

The instructor of this course owns the copyright of all the course materials. This lecture material was distributed only to the students attending the course *ESO208A*: Computational methods in Engineering of IIT Kanpur and should not be distributed in print or through electronic media without the consent of the instructor. Students can make their own copies of the course materials for their use.

### Recap

- Computational methods cannot be studied in isolation of the problem
  - "The purpose of computing is insight, not numbers", Hamming
- Significant digits/figures are the numbers that one can use with confidence
- True error = True value Measured / Computed value
  - approximate error
  - error bound

True error is never known

### Recap

- Types of error
  - Model error
  - Data error
  - Truncation error

Computers are finite

- Round-off error -

- Round-off error originates from the fact that computers retain only a fixed number of significant figures during a calculation
- In addition, because computers use a base-2 representation, they cannot precisely represent certain base-10 numbers.

$$208$$
= 1\ 0\ 0000

$$22^{6}2^{5}2^{2}2^{2}2^{2}2^{2}$$
= 1\times 2\ + \times 2^{6} + \times 208

= 208

$$208.625 = 1\010000 \cdot 101$$

$$2^{1}2^{2}2^{3}$$
= 1\times 2^{1} + 0 + 1\times 2^{\frac{1}{2}}0^{6}62^{6}

Number representation in computers

- Integer
- Fixed point
- Floating point

Integer-unsigned (0,1,2), signed (-1,-2,1,2,0)

For a 4-bit machine how many integers one can store?

1-bit: one space in binary computer

4-bit: nibble

8-bit: one byte

32-bit: word

64-bit: double word

For a 4-bit machine how many integers one can store?

#### You can store $2^4 = 16$ numbers

- 0-15 in case of unsigned numbers
- In case of signed, the first bit holds the sign. The remaining 3 bits can hold binary number from 000 to 111, i.e. in decimal numbers from 0 to 7
- The range should be from -7 to 7, but the range is -8 to 7.
- The +ve limit in generalized form can be obtained by 2<sup>n-1</sup>-1, n is number of bits.




- Fixed point-  $\pi = 3.14, \frac{1}{\sqrt{2}} = 0.71$ 
  - Location of decimal point is fixed (two places after decimal)
  - Useful for hand calculator
- Floating point

Floating point numbers

$$x = \pm mb^{p}$$

$$TT = 0.314 \times 10^{1}$$
 $1/\sqrt{2} = 0.707 \times 10^{\circ}$ 

To store a floating point number, a computer word is divided into three parts



TEEE 754

$$C4.bit$$
 $1bt$ 
 $11bts$ 
 $52bits$ 

TEEE 754.7

 $(2008)$ 
 $11bts$ 
 $-2'' - 0 to 2047$ 
 $6x(ess-b)$ 
 $6x(ess-b)$ 

What we did so far was for binary, in case of decimal the maximum decimal power can be

$$m = 2^{1024} = m \cdot 10^{9}$$

$$q = \frac{\log(2)}{\log(10)} \cdot 1024$$

$$= 308$$

$$10^{308}$$

## **Summary**

Number representation in Computers

- Integers
- Fixed Point
- Floating Point