Home — autonomy running

Bag playback, 11:46:02 CDT. Every value is a field recorded in autonomy_demo_0.

CAVS Center for Advanced Vehicular Systems

Autonomous Vehicle Testing

LIVE · bag playback · autonomy_demo_0

SAFETY FILTER	NAV2	DRIVE BRIDGE	E-STOP	11:46:02
OK	active	LIVE	clear	Sep 11, 2026 CDT

DRIVE STATUS

AUTONOMY

Navigating through 2 poses
to (14.50, −12.29)

Speed	1.58 m/s
Commanded speed	1.40 m/s
Commanded turn	+0.040 rad/s
Active source	autonomy
Autonomy active	true


CAMERAS

Camera | LiDAR | Faults



Latest frame from /cam_0, /cam_1, /cam_2 image_raw · once per second

NAVIGATION




driven (/dlio path) /plan obstacle

SYSTEMS HEALTH

Safety filter	ok
Nav2	Managed nodes are active
Drive bridge	LIVE (transmitting)
Odometry age	0 ms
LiDAR age	6 ms
TF age	33 ms
Command age	49 ms

LiDAR TOP VIEW · OCCUPANCY GRID



occupied
free
vehicle footprint

/local_costmap/voxel_layer
30 × 30 m, 0.2 m cells
/local_costmap/published_footprint

STOP STATE

/mtx/estop	no message yet
Arbiter e-stop	false
Arbiter inhibit	none
Collision monitor	no message yet

LOG · WARN / ERROR

11:45:56	WARN	command_arbiter: mode=AUTONOMY autonomy_requested=True autonomy
11:45:56	WARN	controller_server: No progress checker was specified in parameter
11:45:56	WARN	controller_server: No goal checker was specified in parameter 'cu
11:45:56	WARN	web_ui: web: operator sent

Home | Map | Sensors | Logs | Faults

No active alerts

Home — operator STOP, e-stop latched

Bag playback, 11:46:53 CDT. Recorded STOP at 11:46:52.8.

CAVS Center for Advanced Vehicular Systems

Autonomous Vehicle Testing

LIVE · bag playback · autonomy_demo_0

SAFETY FILTER	NAV2	DRIVE BRIDGE	E-STOP	
OK	active	LIVE	LATCHED	11:46:53 Sep 11, 2026 CDT

E-STOP LATCHED · 11:46:52.8 web: STOP pressed by operator · command_arbiter: SOFTWARE E-STOP LATCHED

DRIVE STATUS

E-STOP
SOFTWARE E-STOP LATCHED
STOP pressed by operator

Speed	0.12 m/s
Commanded speed	inactive
Commanded turn	inactive
Active source	none
Autonomy active	false


CAMERAS

Camera | LiDAR | Faults

CAM 0 | CAM 1 | CAM 2

Latest frame from /cam_0, /cam_1, /cam_2 image_raw · once per second

NAVIGATION




driven (/dlio path) /plan obstacle

SYSTEMS HEALTH

Safety filter	ok
Nav2	Managed nodes are active
Drive bridge	LIVE (transmitting)
Odometry age	3 ms
LiDAR age	12 ms
TF age	72 ms
Command age	48 ms

LiDAR TOP VIEW · OCCUPANCY GRID



occupied
free
vehicle footprint

/local_costmap/voxel_layer
30 × 30 m, 0.2 m cells
/local_costmap/published_footprint

STOP STATE

/mtx/estop	true
Arbiter e-stop	true
Arbiter inhibit	estop
Collision monitor	clear

LOG · WARN / ERROR

11:46:52	WARN	web_ui: web: goal finished CANCELED
11:46:52	ERROR	bt_navigator_navigate_: Failed to get result for follow_path in node h
11:46:52	WARN	command_arbiter: mode=ESTOP autonomy_requested=False autonomy_a

Home | Map | Sensors | Logs | Faults

11:46:52 · SOFTWARE E-STOP LATCHED

Changes from v1

Only fields recorded in the bag are shown. Anything that had to be calculated has been removed.

Header	Localization and Comms removed (no recorded status). Now Safety filter, Nav2, Drive bridge and E-stop, each read directly from /mtx/velocity_filter/status, /diagnostics and /mtx/estop.
Drive status	Speed is /mtx/odom twist.linear.x. Commanded speed and turn are /mtx/cmd_vel_autonomy. Goal text is the bt_navigator log line. Waypoint number removed (inferred).
Cameras	Frame rate and gap labels removed (calculated). Only the latest image of each camera.
Navigation	Driven path is the recorded /dlio/odom_node/path. Vehicle drawn from /local_costmap/published_footprint. Inferred WP 1 removed; goal is the last pose of /plan.
Systems health	Feed rates removed (calculated). Rows are recorded fields: safety filter ok and reasons, Nav2 health, drive bridge, and the odometry, LiDAR, TF and command ages from /mtx/velocity_filter/status.
LiDAR	Occupancy grid from /local_costmap/voxel_layer: only cells the LiDAR hit (occupied / free), no safety margin. Vehicle from the recorded footprint. No local path overlay (needs a frame transform).
Stop triggers	Removed: every trigger is a calculation on message timing. Replaced by Stop state, read from /mtx/estop, /mtx/arbiter_status and the collision monitor.
Mission	Distances removed (calculated). Replaced by the WARN / ERROR lines from /rosout.
Page 2	Shows the recorded operator STOP and e-stop at 11:46:52, not a trigger stop.