SIMULATION TOOL CISCO PACKET TRACER

Experiment: Installation and Basic Network Configuration Using Cisco Packet Tracer

AIM

To install Cisco Packet Tracer and create a simple network consisting of two computers connected through a switch, configure IP addresses, and verify connectivity.

REQUIREMENTS

Computer/Laptop, Internet connection, Cisco Packet Tracer software, and a Cisco Networking Academy or Skills for All account.

INTRODUCTION

Cisco Packet Tracer is a network simulation software used to design and test computer networks. It provides virtual routers, switches, computers, cables and other networking devices, allowing network configurations to be tested without physical hardware.

INSTALLATION PROCEDURE

Step 1: Open the Cisco Networking Academy or Skills for All website and sign in with your account.

Step 2: Go to the Packet Tracer download section and select the installer suitable for your operating system.

Step 3: After the download is complete, locate the installer and double-click it to start the installation.

Step 4: Read the License Agreement, select the option to accept the agreement, and click Next.

Step 5: Select the installation folder. The default folder can be used unless another location is required.

Step 6: Select the required shortcuts and click Next.

Step 7: Click Install and wait until the installation is completed.

Step 8: Click Finish and open Cisco Packet Tracer.

Step 9: Sign in using the required Cisco account. Packet Tracer is now ready to use.


PROCEDURE FOR BASIC NETWORK SETUP

1. Open Cisco Packet Tracer.
2. From End Devices, place two PCs in the workspace.
3. From Network Devices → Switches, place one switch.
4. Select the Copper Straight-Through cable and connect PC0 to the switch.
5. Connect PC1 to another port of the switch using the same cable.
6. Open PC0 → Desktop → IP Configuration and enter the following:
    - IP Address: 192.168.1.10
    - Subnet Mask: 255.255.255.0
7. Open PC1 → Desktop → IP Configuration and enter the following:
    - IP Address: 192.168.1.11
    - Subnet Mask: 255.255.255.0
8. Open PC0 → Desktop → Command Prompt and type:

```
ping 192.168.1.11
```

NETWORK CONFIGURATION

Device	IP Address	Subnet Mask
PC0	192.168.1.10	255.255.255.0
PC1	192.168.1.11	255.255.255.0



RESULT

Cisco Packet Tracer was installed successfully. A basic LAN was created using two PCs and a switch, and connectivity between the PCs was successfully verified using the ping command.