




Topology for ACL



Pinging from PC to Server




Standard ACL Enable



```
R1#
R1#
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#access
R1(config)#access-list 10 permit 10.0.0.10 0.0.0.0
R1(config)#int e0/0
R1(config-if)#ip access
R1(config-if)#ip access-group 10 in
R1(config-if)#do acces
R1(config-if)#do acces-l
R1(config-if)#do sh acces-list
                        ^
% Invalid input detected at '^' marker.


R1(config-if)#do sh access-list
Standard IP access list 10
    10 permit 10.0.0.10
R1(config-if)#
```


Linux Server IP configuration



After enable of Extended ACL



The 10.10 can only use 172.50.0.10 Server, 10.20 can only use 172.50.0.20





DNS Server

Provided name to the IP



ACL router configuration, Enabled Extended ACL for UDP, TCP, ICMP

```
R1
R1(config)#$t icmp 10.0.0.0 255.255.255.255 200.12.56.10 0.0.0.0 eq 53
access-list 100 permit icmp 10.0.0.0 255.255.255.255 200.12.56.10 0.0.0.0 eq 53
^
% Invalid input detected at '^' marker.

R1(config)#$t icmp 10.0.0.0 255.255.255.255 200.12.56.10 0.0.0.0
R1(config)#do sh access
R1(config)#do sh access-
R1(config)#do sh access-list
Extended IP access list 100
    10 permit udp any host 200.12.56.10 eq domain
    20 permit icmp any host 200.12.56.10 (4 matches)
R1(config)#
R1(config)#
R1(config)#access-list 100 permit tcp 10.0.0.20 0.0.0.0 172.50.0.20 0.0.0.0 eq$
R1(config)#$ 100 permit tcp 10.0.0.10 0.0.0.0 172.50.0.10 0.0.0.0 eq 80
R1(config)#
R1(config)#do sh access-list
Extended IP access list 100
    10 permit udp any host 200.12.56.10 eq domain
    20 permit icmp any host 200.12.56.10 (4 matches)
    30 permit tcp host 10.0.0.20 host 172.50.0.20 eq www
    40 permit tcp host 10.0.0.10 host 172.50.0.10 eq www
R1(config)#
```