Nagios XI

安裝配置嚮導(Wizards)



目的

本文檔介紹如何獲取和安裝 Nagios XI 的配置嚮導。

目標聽眾

本文檔供希望為 Nagios XI 安裝附加嚮導的 Nagios 管理員使用

,因為 Nagios Exchange 上有可以提供附加功能的第三方配置嚮導(Wizards)。


配置嚮導(Wizards)概述

配置嚮導是 Nagios XI 的插件,使最終用戶可以輕鬆地使用 Nagios XI 監控新設備、服務和應用程序。 嚮導為原本可能是複雜任務的任務提供了一個用戶友好的界面。

它們對於 Nagios XI 的新用戶特別有用,它們可以創建所有相關的監控配置

,而無需了解 Nagios XI 在後端的工作原理。

可以從導航菜單配置訪問安裝在 Nagios XI 中的配置嚮導。



Edit by james.hsu@ibm.com mobile-phon: 0988707668

Network: | Enterprise | Support | Library | Project | Exchange | [+]

Nagios XI

安裝配置嚮導(Wizards)

提示: 您可以通過以下方式快速過濾配置嚮導列表:

- 在搜索框中鍵入,例如 wind 將顯示所有帶有 wind 字的嚮導 (例如 Windows wizards)
- 單擊"搜索"框右側的圖標,例如, Windows 圖標現在將僅顯示使用搜索出現的 Windows 嚮導,但還會

獲得新 Wizards

其他配置嚮導可以從 Nagios Exchange 網站獲得:

https://exchange.nagios.org/directory/Addons/Configuration/Configuration-Wizards

<u>N</u>agios[®] Home Directory About Home Directory Addons Configuration Configuration Wizards Search Exchange Category: Configuration Wizards search. Nagios XI configuration wizards make it easy to extend Nagios for your organization. Configuration wizards provide users with easy. Search step-by-step instructions for monitoring new hosts and services with Nagios. Advanced Search For more information on Nagios XI, visit www.nagios.com/products/nagiosxi Search All Sites **Submit Your Nagios Project!** Help build Nagios Exchange for yourself and the entire the Nagios Community by your Nagios project to the site. It's easy - just create an account, login, and Go add a new listing. Read the FAQ for instructions. Nagios Live Webinars **Category Listings:** Let our experts show you how Nagios can help your There are 65 Listings in this Category. List your addon or plugin here! organization. Exchange Server Monitoring Wizard Featured ***

Edit by james.hsu@ibm.com mobile-phon: 0988707668

Nagios®

Q

www.nagios.com/products/nagiosxi

performance metrics.

Register Now

Contact Us Phone: 1-888-NAGIOS-1 Email: sales@nagios.com

> Username Password

Login

This Nagios XI wizard allows you to easily monitor Microsoft Exchange servers - including service states, protocol availability, and

The Log Server Monitoring Wizard allows you to monitor any query against all logs in Nagios Log Server.

Nagios XI

安裝配置嚮導(Wizards)


在 Nagios Exchange 上,您將找到外部各方發布的配置嚮導,以及 Nagios XI 附帶的所有現有嚮導。

本指南將上傳 ibmservice / ibmicustomsql 演示嚮導,該嚮導可在 https://github.com/IBM/nagios-for-i 上找到。 下載 ibmservice.zip 及 ibmicustomsql.zip 文件


,您就會在下一步中看到如何上傳它。

Wizard 安裝

在 Nagios XI 中安裝新的配置嚮導非常簡單。 導航到 Admin > System Extensions > Manage Config Wizards.




單擊 "Browse" 按鈕以選擇要安裝的新嚮導。



使用出現的窗口選擇您之前下載的配置嚮導文件(.zip 擴展名),然後單擊 Open。


單擊 Upload & Install 按鈕上傳配置嚮導



Edit by james.hsu@ibm.com mobile-phon: 0988707668

Nagios XI


安裝配置嚮導(Wizards)



Wizard 上傳後,您將收到一條消息

- ,說明它已安裝
- ,並且會出現在嚮導列表中。 (列表很長要往下拉才看得到)

現在,當您導航回配置菜單時,您將在列表中看到新的Wizard。



整理起來

這完成了有關如何在 Nagios XI 中安裝配置嚮導的文檔。如果您有其他問題或其他與支持相關的問題,請訪問我們的 Nagios 支持論壇:

https://support.nagios.com/forum

Nagios 支持知識庫也是一個很好的支持資源:

https://support.nagios.com/kb

Edit by james.hsu@ibm.com mobile-phon: 0988707668

IBM-I/HUM 對接訊息

進入配置 Wizerd 第二個步驟開始需要輸入重要信息 如下:。

Configuration Wizard: IBM i service - Step 2						*
Server Details		_				
IP Address:	10.129.61.25	路定址				
Host Name:	ibm-i.domain-name.com The name you'd like to have associated with this host.	⇒域名	Server Type:	IBM i (Default) > 服務器類 Determines whether of not data between the Nagio		is
User Profile:	user-name Specify the user profile of IBM i server.		Password:	Specify the passowrd of the user profile.	長 帳號密碼	
SSL Encryption:	Disabled (Default) > 可選擇加密與否 Determines whether or rot data between the Nagios XI server and IBM i server is encrypted.					

在頁面下方還有一組關於 Disk 的帳號密碼如下:。

If you click the checkbox for **Disk Status** above, you must specify the SST Profile in the fields below. The password level for the SST profile in Dedicated Service Tools (DST) must be set to level 2. To change password level, go to STRSST-> Option 8: Work With Service Tools Server Security and Devices -> Option 4: Change service tools password level.

Once the level is changed, the password itself must be changed for the new level to take effect.

SST Profile:		SST Password:	
--------------	--	---------------	--

關於 IBM-i 服務器端的防火墻端口如下:。

Service Name	Number
as-Central	8470
as-Database	8471
as-dtaq	8472
as-file	8473
as-netprt	8474
as-rmtcmd	8475
as-signon	8476
as-svrmap	449