



SERVER OVERVIEW 1.0

Created by: Jamie Briggs

Institution: University of Strathclyde

Department: Electronic and Electrical Engineering

Project Lead: Aran Eales - arran.eales@strath.ac.uk

Date Created: 25.03.25

Version: 1.0

Last Updated: 25.03.25

This documentation provides technical guidance for accessing and working with the Malawi Microgrids Virtual Integrated Project (VIP) server. The server is managed by Strathclyde's IT Services and acts as the primary backend for hosting data, scripts, and dashboards related to the project.

Server Details

Property	Value
FQDN	eee-microgrid.eee-vc.strath.ac.uk
Operating System	Windows Server 2019
vCPUs	2
RAM	Dynamic, up to 16GB
Drives	C: (OS) – 50GB D: (Data) – 100GB
Purpose	Hosting MySQL database, Python scripts, and a dashboard
Python Env	Installed via Miniconda
Database	MySQL
Managed by	Strathclyde IT Services

2. ACCESSING THE SERVER

2.1 Contact for Access

To request access, contact Strathclyde IT Services with your reason for needing admin rights on the server.

IT Contact Email(s):

Alan Williamson - alan.williamson@strath.ac.uk

Aaron Ferguson - a.k.ferguson@strath.ac.uk

2.2 Prerequisites

You will need:

- An **admin account** on the Strathclyde network
 - A **Strathclyde-managed device**, or VPN access if remote
 - Access to **Remote Desktop Connection**
-

2.3 VPN Setup (For Remote Access)

If you're off-campus or using a personal device, you must connect to the VPN first.

-  [Strathclyde VPN Setup Guide](#)
-

2.4 Connecting to the Server

1. Log into a Strathclyde-managed computer or connect via VPN.
2. Open **Remote Desktop Connection** (Start → search for it).
3. In the "Computer" field, enter:

```
eee-microgrid.eee-vc.strath.ac.uk
```

4. Click **Connect**, then click **Connect** again when prompted.
5. Enter your **Strath admin credentials** (same as your login).

6. If a certificate warning appears:

"The identity of the remote computer cannot be verified. Do you want to connect anyway?"

Click **Yes**.

7. You should now be connected to the server desktop.

 [Insert Image 1: Remote Desktop Connection window]

 [Insert Image 2: Login prompt]

 [Insert Image 3: Security warning]

2.5 Notes & Tips

- Admin accounts must be requested individually — they are not shared.
- Once logged in, the user environment is pre-configured with Python, Miniconda, and database access.
- If connection issues occur, confirm VPN is active or check firewall permissions.