
# **Project 1 Tutorial**





# **Common commands**

- cd: change directory
- make: compile the source code using the accompany Makefile
- sudo: using the root permission
- rm: remove files
- Is: list the files in the current directory
- .....
- The 10 Most Important Linux Commands
- 50 Most Frequently Used UNIX / Linux Commands (With Examples)





Create, load, unload a kernel module





# **Listing Kernel Modules**

Ismod: list all kernel modules that are currently loaded

```
zhisheng@zhisheng-ubuntu: ~
File Edit View Terminal Help
zhisheng@zhisheng-ubuntu:~$ lsmod
Module
                       Size Used by
binfmt misc
                       6523 1
snd intel8x0
                      25652 2
                     100646 1 snd intel8x0
snd ac97 codec
ac97 bus
                      1002 1 snd ac97 codec
snd pcm oss
                      35308
snd mixer oss
                      13746 1 snd pcm oss
                      70918 3 snd intel8x0, snd ac97 codec, snd pcm oss
snd pcm
                      1338 0
snd seg dummy
snd seg oss
                      26722 0
snd seg midi
                      4557 0
snd rawmidi
                      19056 1 snd seg midi
snd seg midi event 6003 2 snd seg oss, snd seg midi
snd seq
                      47295
                             6 snd seq dummy, snd seq oss, snd seq midi, snd seq m
idi event
                      19130 2 snd pcm, snd seq
snd timer
                       5700 5 snd seq dummy, snd seq oss, snd seq midi, snd rawmi
snd seg device
di,snd seq
                       5259 0
ppdev
fbcon
                      35102
                            71
tileblit
                            1 fbcon
                       1999
                       7557 1 fbcon
font
bitblit
                       4707 1 fbcon
```





# A Simple Kernel Module


```
simple.c (~/Desktop/4320) - gedit
File Edit View Search Tools Documents Help
                          🔛 🦣 Undo 🥟 🐰 🖺 🖺 🔾 😪
       Open v Save
simple.c 🗱
#include ux/init.h>
#include ux/module.h>
#include ux/kernel.h>
/* This function is called when the module is loaded. */
int simple init(void)
printk(KERN INFO "Loading Module\n");
return 0:
/* This function is called when the module is removed. */
void simple exit(void) {
printk(KERN INFO "Removing Module\n");
/* Macros for registering module entry and exit points. */
module init( simple init );
module exit( simple exit );
MODULE LICENSE("GPL");
MODULE DESCRIPTION("Simple Module");
MODULE AUTHOR ("SGG");
                                                   C ▼ Tab Width: 8 ▼ Ln 9, Col 2
                                                                                        INS
```



# **Compile the Source Code**

simple.c and Makefile in folder "4230"

make: compile the source code





kerne

modules.order

#incl

#incl

simple.mod.c

4320


simple.ko



### **Load the Kernel Module**

sudo insmod: load a kernel module

```
zhisheng@zhisheng-ubuntu: ~/Desktop/4320
File Edit View Terminal Help
zhisheng@zhisheng-ubuntu:~/Desktop/4320$ sudo insmod simple.ko
[sudo] password for zhisheng:
zhisheng@zhisheng-ubuntu:~/Desktop/4320$ lsmod
Module
                        Size Used by
                         654 8
simple
DINTMT MISC
                        0523 1
snd intel8x0
                       25652 2
snd ac97 codec
                      100646 1 snd intel8x0
ac97 bus
                        1002 1 snd ac97 codec
snd pcm oss
                       35308 0
snd mixer oss
                       13746 1 snd pcm oss
                       78918 3 snd intel8x8, snd ac97 codec, snd pcm oss
snd pcm
snd seg dummy
                       1338 0
snd seg oss
                       26722 0
snd seg midi
                       4557 0
snd rawmidi
                       19856 1 snd seg midi
snd seq midi event
                       6003 2 snd seg oss, snd seg midi
                       47295
                             6 snd seg dummy, snd seg oss, snd seg midi, snd seg m
snd seq
idi event
snd timer
                       19130 2 snd pcm, snd seq
                        5700 5 snd seq dummy, snd seq oss, snd seq midi, snd rawmi
snd seg device
di, snd seq
ppdev
                        5259 0
fbcon
                       35102 71
```



#### Remove the Kernel Module


- sudo rmmod: remove a kernel module
- dmesg: check kernel log buffer

```
zhisheng@zhisheng-ubuntu: ~/Desktop/4320
File Edit View Terminal Help
    27.150636] type=1505 audit(1516325807.227:9):
                                                   operation="profile replace" p
id=689 name="/sbin/dhclient3"
    27.154410] type=1505 audit(1516325807.231:10):
                                                    operation="profile replace"
pid=689 name="/usr/lib/NetworkManager/nm-dhcp-client.action"
    27.154681] type=1505 audit(1516325807.231:11):
                                                    operation="profile replace"
pid=689 name="/usr/lib/connman/scripts/dhclient-script"
    27.316506] type=1505 audit(1516325807.395:12):
                                                    operation="profile load" pid
=690 name="/usr/bin/evince"
    27.328529] type=1505 audit(1516325807.407:13):
                                                    operation="profile load" pid
=690 name="/usr/bin/evince-previewer"
    27.332047] type=1505 audit(1516325807.407:14):
                                                    operation="profile load" pid
=690 name="/usr/bin/evince-thumbnailer"
                                                    operation="profile load" pid
    27.433177 type=1505 audit(1516325807.511:15):
=693 name="/usr/lib/cups/backend/cups-pdf"
    27.433729] type=1505 audit(1516325807.511:16):
                                                    operation="profile load" pid
=693 name="/usr/sbin/cupsd"
    27.476501] type=1505 audit(1516325807.555:17):
                                                    operation="profile load" pid
=694 name="/usr/sbin/tcpdump"
    37.288133] eth0: no IPv6 routers present
 1605.095337] Clocksource tsc unstable (delta = 4687093270 ns)
 1605 1187501 Switching to clocksource 3CD1 DM
 2114.592436] Loading Module
 2349.372386] Removing Module
zhisheng@zhisheng-ubuntu:-/Desktop/4320$
```



- Kernel data structure
- An application of kernel module management






- Kernel data structure include file: linux/list.h>
- Define a linked list


```
struct birthday
  int month;
  int day;
  int year;
    struct list_head list;
);
J##
* The following defines and initializes a list_head object named birthday_list
*/
static LIST_HEAD(birthday_list);
```





At module entry point, define each element in the list

```
int simple_init(void)
{
  /* the pointer for memory allocation */
  struct birthday *person;
    person_one = kmalloc(sizeof(*person_one), GFP_KERNEL);
    person_one->month = 8;
    person_one->day = 13;
    person_one->year = 1995;
  INIT_LIST_HEAD(&person_one->list);
    /* add the new node */
  list_add_tail(&person_one->list, &birthday_list);
```



Traversing the Linked List

```
struct birthday *ptr;
list_for_each_entry(ptr, &birthday_list, list) {
   /* on each iteration ptr points */
   /* to the next birthday struct */
}
```






At module exit point, remove each element from the list

```
struct birthday *ptr, *next

list_for_each_entry_safe(ptr,next,&birthday_list,list) {
   /* on each iteration ptr points */
   /* to the next birthday struct */
   list_del(&ptr->list);
   kfree(ptr);
}
```



 After compiling, loading, and removing the module, kernel log shows

```
zhisheng@zhisheng-ubuntu: ~/Desktop/4320/proj1
File Edit View Terminal Help
   27.332047] type=1505 audit(1516325807.407:14):
                                                   operation="profile load" pid
=690 name="/usr/bin/evince-thumbnailer"
   27.433177] type=1505 audit(1516325807.511:15):
                                                   operation="profile load" pid
=693 name="/usr/lib/cups/backend/cups-pdf"
   27.433729] type=1505 audit(1516325807.511:16):
                                                   operation="profile load" pid
=693 name="/usr/sbin/cupsd"
   27.476501] type=1505 audit(1516325807.555:17):
                                                   operation="profile load" pid
=694 name="/usr/sbin/tcpdump"
   37.288133] eth0: no IPv6 routers present
 1605.095337] Clocksource tsc unstable (delta = 4687093270 ns)
 1605.118750] Switching to clocksource acpi pm
 2114.592436] Loading Module
 2349.372386] Removing Module
 5235.577735] Loading Module
 5235.577746] Birthday: Month 10 Day 22 Year 1963
5235.577753] Birthday: Month 8 Day 13 Year 1995
 5235.577761] Birthday: Month 9 Day 2 Year 1998
 5235.577767] Birthday: Month 8 Day 12 Year 1963
 5398.896154] Removing Module
 5398.896163] Removing 10 22 1963
 5398.896169] Removing 8 13 1995
 5398.896175] Removing 9 2 1998
 5398.896181] Removing 8 12 1963
zhisheng@zhisheng-ubuntu:-/Desktop/4320/proj1$
```