

Exercise 2: Creating Volumes and Junction Paths

In this exercise, you create two NetApp FlexVol volumes and verify the namespace for the storage VM. Later, you log in as root to the Linux client and mount the storage VM namespace.


Objectives



This exercise focuses on enabling you to do the following:

- Create FlexVol volumes
- Mount a storage VM namespace

Task 1: Create FlexVol Volumes

In this task, you create two FlexVol volumes and verify the namespace for the storage VM.

Step	Action
1-1	From the ONTAP System Manager menu, select Storage > Volume .
1-2	Click + Add . 

Step	Action
1-3	In the Add volume dialog box, specify the following details: - Name: Vol1 - Capacity: 20 MiB - Storage VM: SVMNFS1 
1-4	Click More options .
1-5	Review the Access permissions section and set the Grant access to host option to default, if needed. 
1-6	Click Save .

Step	Action
1-7	Repeat steps 1-2 to 1-6 and create three more volumes by specifying the following details: - Name: Vol2 - Capacity: 20 MiB - Storage VM: SVMNFS1 - Name: data - Capacity: 100 MiB - Storage VM: SVM1 - Name: projects - Capacity: 50 MiB - Storage VM: SVM1

Task 2: Mount a Storage VM Namespace

In this task, you log in as root to the Linux client and mount the storage VM namespace.

Step	Action
2-1	Use PuTTY to log in to the Ubuntu client as root.
2-2	Change the directory to the mount folder. <code>cd /mnt</code>
2-3	Create a mount folder that is named SVMNFS1 . <code>mkdir SVMNFS1</code>
2-4	Verify the permissions. <code>ls -l</code> Sample output: <pre>root@ubuntu:/mnt# ls -l total 8 drwxr-xr-x 2 root root 4096 Apr 1 2024 nas drwxr-xr-x 2 root root 4096 Dec 4 19:49 SVMNFS1</pre>
2-5	Mount the storage VM namespace at the new folder. <code>mount -o nfsvers=3 192.168.0.52:/ /mnt/SVMNFS1</code>
2-6	Answer the following questions: - Were you able to mount the storage VM namespace? - Why or why not?

Step	Action
2-7	Run the following command to display information about the junction paths: <pre>showmount -e 192.168.0.52</pre> <pre>root@ubuntu:/mnt# showmount -e 192.168.0.52</pre> <pre>Export list for 192.168.0.52:</pre>
2-8	What could be the reason why the export list is empty, indicating that there are no NFS exports (junction paths) available or visible to the client from the NFS server?

End of exercise