

24%

OS VIEW (Win)



SINGLE TAP

DOUBLE TAP

TRIPLE TAP

SHIFT

SWITCH

ONE FINGER DOWN

○ ○ ○ ○ ● a
 ○ ○ ○ ● ○ e
 ○ ○ ● ○ ○ i
 ○ ● ○ ○ ○ o
 ● ○ ○ ○ ○ u

TWO FINGERS TOGETHER

○ ○ ○ ● ● n
 ○ ○ ● ● ○ t
 ○ ● ● ○ ○ l
 ● ● ○ ○ ○ s

TWO FINGERS SKIPPING ONE

○ ○ ● ○ ● d
 ○ ● ○ ● ○ m
 ● ○ ● ○ ○ z

TWO FINGERS SKIPPING TWO

○ ● ○ ○ ● k
 ● ○ ○ ● ○ b

LOOKS LIKE Y AND W

● ○ ○ ○ ● y
 ● ○ ● ○ ● w

ONE FINGER UP

● ● ● ● ○ h
 ● ● ● ○ ● c
 ● ● ○ ● ● v
 ● ○ ● ● ● j
 ○ ● ● ● ● r

ONE FINGER CHASING TWO

○ ● ● ○ ● g
 ● ● ○ ● ○ x

TWO FINGERS CHASING ONE

○ ● ○ ● ● f
 ● ○ ● ● ○ q

THREE FINGERS SKIPPING TWO

● ● ○ ○ ● Enter
 ● ○ ○ ● ● p

THREE FINGERS TOGETHER

○ ○ ● ● ● ~~Toggle Shift mode~~ L-shift(+)
 ○ ● ● ● ○ Backspace
 ● ● ● ○ ○ Toggle Switch mode

ALL FINGERS TOGETHER

● ● ● ● ● Space

LOAD DEFAULT MAP

CLEAR MAP

Switch = Num + Nav + Modifiers (?)

OS VIEW (Win)



SINGLE TAP

DOUBLE TAP

TRIPLE TAP


SHIFT

SWITCH

ONE FINGER DOWN



ONE FINGER UP



TWO FINGERS TOGETHER



ONE FINGER CHASING TWO



TWO FINGERS SKIPPING ONE



TWO FINGERS CHASING ONE



TWO FINGERS SKIPPING TWO




THREE FINGERS SKIPPING TWO



LOOKS LIKE Y AND W



THREE FINGERS TOGETHER




ALL FINGERS TOGETHER



LOAD DEFAULT MAP

CLEAR MAP

Hold Tap = Shift of Switch



SINGLE TAP

DOUBLE TAP

TRIPLE TAP

SHIFT

SWITCH

ONE FINGER DOWN

○ ○ ○ ○ ●	L-Shift 1
○ ○ ○ ● ○	L-Shift 2
○ ○ ● ○ ○	L-Shift 3
○ ● ○ ○ ○	L-Shift 4
● ○ ○ ○ ○	L-Shift 5

TWO FINGERS TOGETHER

○ ○ ○ ● ●	Take pic Home
○ ○ ● ● ○	PageUp
○ ● ● ○ ○	End
● ● ○ ○ ○	L-Shift 9

TWO FINGERS SKIPPING ONE

○ ○ ● ○ ●	L-Shift . (>)
○ ● ○ ● ○	L-Shift , (<)
● ○ ● ○ ○	L-Shift 8

TWO FINGERS SKIPPING TWO

○ ● ○ ○ ●	PageDown
● ○ ○ ● ○	L-Shift 7

LOOKS LIKE Y AND W

● ○ ○ ○ ●	L-Shift 6
● ○ ● ○ ●	L-Shift ` (~)

ONE FINGER UP

● ● ● ● ○	L-Shift 0
● ● ● ○ ●	L-Shift ; (:)
● ● ○ ● ●	L-Shift = (+)
● ○ ● ● ●	L-Shift] (})
○ ● ● ● ●	L-Shift [({)

ONE FINGER CHASING TWO

○ ● ● ○ ●	L-Shift \ ()
● ● ○ ● ○	L-Shift - (_)

TWO FINGERS CHASING ONE

○ ● ○ ● ●	Voice over L-Shift / (?)
● ○ ● ● ○	L-Shift ' (")

THREE FINGERS SKIPPING TWO

● ● ○ ○ ●	L-Windows (+)
● ○ ○ ● ●	F5

THREE FINGERS TOGETHER

○ ○ ● ● ●	Shift mode lock L-shift Lock
○ ● ● ● ○	F11
● ● ● ○ ○	Disabled Switch Lock

ALL FINGERS TOGETHER

● ● ● ● ●	L-Shift + Tab
-----------	---------------