

Practical No. 10

Image name

WebServerAMI

Maximum 127 characters. Can't be more than 127 characters.

Image description - optional

Lab AMI for Web Server

Maximum 255 characters

1

Target type

Indicate what resource type you want to target. Only the selected resource type will be used.

☒ **Instances**
Supports load balancing to instances in a VPC. Integrate with Auto Scaling Groups or ECS services for automatic management.
Suitable for: ALB NLB GWLB

☐ **Lambda function**
Supports load balancing to a single Lambda function. ALB required as traffic source.
Suitable for: ALB

Target group name

Name must be unique per Region per AWS account.

LabGroup

2.1

Availability Zones and subnets [Info](#)

Select at least two Availability Zones and a subnet for each zone. A load balancer must be in the same Availability Zone as the subnets.

☒ **us-east-1a (use1-az6)**

Subnet

Only CIDR blocks corresponding to the load balancer IP address type are used.

subnet-0afe47497dd9b3296 (Public Subnet 1)
10.0.0.0/24

☒ **us-east-1b (use1-az1)**

Subnet

Only CIDR blocks corresponding to the load balancer IP address type are used.

subnet-02fff44236280b4f6 (Public Subnet 2)
10.0.2.0/24

2.2

Forward to target group [Info](#)

Choose a target group and specify routing weight or [create target group](#).

Target group

LabGroup

Target type: Instance, IPv4 | Target stickiness: Off

2.2

VPC

Choose the VPC that defines the virtual network for your Auto Scaling group.

vpc-080a4a7165c4479d6 (Lab VPC)
10.0.0.0/16

[Create a VPC](#)

Availability Zones and subnets

Define which Availability Zones and subnets your Auto Scaling group can use in the chosen VPC.

Select Availability Zones and subnets

use1-az1 (us-east-1b) | subnet-07567b700005df79a (Private Subnet 2) X
10.0.3.0/24

use1-az6 (us-east-1a) | subnet-0f23337f2d10bd846 (Private Subnet 1) X
10.0.1.0/24

3.2

Desired capacity

Specify your group size.

2

3.3

Name

Auto Scaling group name

Enter a name to identify the group.

Lab Auto Scaling Group

Must be unique to this account in the current region.

3.2

Min desired capacity

2

Equal or less than desired capacity

Max desired capacity

6

Equal or greater than desired capacity

Automatic scaling - optional

Choose whether to use a target tracking policy [Info](#)

You can set up other metric-based scaling policies and scheduled scaling after creating your Auto Scaling group.

☐ **No scaling policies**
Your Auto Scaling group will remain at its initial size and will not dynamically resize to meet demand.

☒ **Target tracking scaling policy**
Choose a CloudWatch metric and target value to track. The group size will automatically adjust to maintain the target value.

Scaling policy name

LabScalingPolicy

Metric type [Info](#)

Monitored metric that determines if resource utilization is too low or high. If using EC2 metrics, consider enabling detailed monitoring for better accuracy.

Average CPU utilization

Target value

60

3.3

☐	Lab Instance	i-01d65ab29eba6854e	Running
☐	Lab Instance	i-04e6fa52b4c4c04ed	Running

4.1

 Load Test RDS

Meta-Data	Value
InstanceID	i-04e6fa52b4c4c04ed
Availability Zone	us-east-1b

Current CPU Load: 0%

4.2

Name	State	Actions	Actions muted - new	Last state update (UTC)	Conditions
TargetTracking-Lab Auto Scaling Group- AlarmHigh- 59f20bba-553b- 42e0-a485- db0e4330a400	OK	Actions enabled	-	2026-04-01 16:59:31	CPUUtilization > 60 for 3 datapoints within 3 minutes
TargetTracking-Lab Auto Scaling Group- AlarmLow- 569e72a7-a065- 4e1e-8402- cd278753a80c	Insufficient data	Actions enabled	-	2026-04-01 16:57:04	CPUUtilization < 54 for 15 datapoints within 15 minutes

5.1

aws

Load TestRDS

Under High CPU Load! (auto refresh in 5 seconds)

Current CPU Load: 100%

5.2

Name	State
TargetTracking-Lab Auto Scaling Group- AlarmHigh- 59f20bba-553b- 42e0-a485- db0e4330a400	In alarm

5.2

☐	Lab Instance	i-0de2cca84776a7582	Running		t2.micro	2/2 checks passec
☐	Lab Instance	i-054289f2c3170f88b	Running		t2.micro	Initializing
☐	Lab Instance	i-051a5ee7aa8cb7086	Running		t2.micro	2/2 checks passec
☐	Lab Instance	i-0952e2b0f60cb28c4	Running		t2.micro	2/2 checks passec

5.2

Terminate (delete) instance

⚠ On an EBS-backed instance, the default action is for the root EBS volume to be deleted when the instance is terminated. Storage on any local drives will be lost.

Are you sure you want to terminate these instances?

Instance ID

Termination protection

[i-014b2e01586a7951b \(Web Server 1\)](#)

Disabled

To confirm that you want to delete the instances, choose the terminate button below. Instances with termination protection enabled will not be terminated. Terminating the instance cannot be undone.

Skip OS shutdown

This option skips the graceful OS shutdown process. Use only when your instance must be stopped immediately, such as during an emergency or failover.

☐ Skip OS shutdown

Cancel

Terminate (delete)

6.1